

Scratch 3 Walkthrough and Demo

Created by Isaac Wellish



https://learn.adafruit.com/guide-to-scratch-3

Last updated on 2022-12-01 03:27:52 PM EST

© Adafruit Industries Page 1 of 28

Table of Contents

Overview	5
Adafruit Parts	
• Optional	
Walkthrough	6
	_
Block types	7
The different types of code blocks:	
• Motion	
• Looks	
• Sound	
• Events	
• Control	
• Sensing	
Operators Variables	
VariablesMy Blocks	
Extension Blocks	
• Extension blocks	
User Interface	11
• The Block Palette	
The Script Area	
The Stage Area	
• The Sprite Info Pane	
The Costume/Backdrop Pane	
• The Sounds Pane	
Toolbar and Tutorials	
Tips and Tricks	15
Workflow and mistakes	
• Troubleshooting	
What's New in Scratch 3?	15
• A new build	
• Scratch Extensions	
Other updates per the Scratch Wiki:	
Draw Demo!	17
Scratch Code	18
	10
Create a sprite for the pen	
Adding the pen extension blocks Setting up the program.	
Setting up the programForever loop	
• Test it out!	
CPX and MakeCode	23
What is Circuit Playground Express (CPX)?	
• What is MakeCode?	
Create a New Project with MakeCode	
Add the Keyboard and Mouse Extensions in MakeCode	

© Adafruit Industries Page 2 of 28

•	The I	Neo	Pixel	l Pal	lette

- Coding with the accelerometer
- Sending keyboard info
- Uploading the Code

Putting it All Together

27

- Troubleshooting
- What will you create next?

© Adafruit Industries Page 3 of 28

© Adafruit Industries Page 4 of 28

Overview



In this guide we'll delve into the popular programming language Scratch ().


Scratch is a block-based language geared for beginners that lets you create your own interactive stories, animations, games, music, and art.

Scratch is easy to use and requires no prior coding experience!

First we'll do a walkthrough of the basics.

Next we'll cover the updates in the 3rd and newest edition of the language which was released January 2, 2019.

Lastly we'll do some digital painting inside Scratch using a Circuit Playground Express as our "paintbrush" and "palette". See below!



Adafruit Parts

© Adafruit Industries Page 5 of 28

Circuit Playground Express is a great introduction to electronics and programming

1 x Circuit Playground Express (CPX)

https://www.adafruit.com/product/3333

Circuit Playground Express is a great introduction to electronics and programming

1x USB cable

https://www.adafruit.com/product/592

USB A to Micro-B (Plugs into computer to program the CPX)

Optional

1 x Adafruit Circuit Playground Express Enclosure

https://www.adafruit.com/product/3915

A plastic case for the Circuit Playground Express that makes it look pretty.

Walkthrough


The quickest way to get started with Scratch is to jump right in! The programming language is web-based which means there is no downloading necessary. Just head to the website below.

Click here to get started with Scratch!

After entering the Scratch site, click the orange "Start Creating" button.

You will then be taken to the Scratch project editor. This is where all the coding happens!

Follow the short tutorial to learn the basics of how "sprites ()" work in Scratch.




© Adafruit Industries Page 6 of 28

Block types

Scratch is a "block-based ()" programming language. This means instead of writing lines of code to program, we use "blocks ()". Each block has a specific category that describes what its purpose is. Sprites () are the objects that perform actions in a project and these blocks tell the sprites what to do. Code blocks can also tell a stage or backdrop how to behave.


The different types of code blocks:

Motion ()



Define the movement of sprites


Looks ()



Change the appearance of sprites. Gives the ability to change costumes and apply graphic effects.


© Adafruit Industries Page 7 of 28

Sound ()




Play audio by recording sounds, using Midi notes () and more.

Events ()



Trigger scripts or series of code blocks. Consists mainly of hat blocks () which start a script.


Control ()



Dictate the flow of a project. Provide mechanism for "looping" different blocks and scripts.


© Adafruit Industries Page 8 of 28

Sensing ()



Let multiple sprites interact with themselves and/or the stage. Can determine how two sprites collide for example.

Operators ()



Allow various mathematical functions within a project. Can be used to modify variables and strings ().

Variables ()



Used to store data in projects, like a name or a score.


© Adafruit Industries Page 9 of 28


My Blocks



You can create your own blocks!

Extension Blocks






At the bottom left of the screen. These blocks let you connect to hardware or access a number of other block types like the pen, or music blocks.


© Adafruit Industries Page 10 of 28

User Interface

The <u>Scratch user interface</u> () is the area on your screen where the Scratch program exists. The screen is divided into multiple sections or "<u>panes</u> ()" which have different functions from picking blocks to code with, to coding, to seeing your code in action. We will go through the different elements of the interface.




The Block Palette



The block palette is where all the code blocks exist. Blocks are color coded by category. These blocks can be dragged to the scripting area to either code sprites or the stage.


© Adafruit Industries Page 11 of 28

The Script Area



The scripts area is where our code is dragged to and assembled.


The Stage Area



The stage is where we can see our code come to life! For example if we have a "when green flag clicked" event block at the start of our code, we can click the green flag to trigger the code we wrote.


© Adafruit Industries Page 12 of 28

The Sprite Info Pane



The sprite info pane is where we can find info about our sprites as well as manipulate them. Access this pane by clicking on the thumbnail of the desired sprite. This area also allows us to delete and create new sprites.


The Costume/Backdrop Pane



The costume and backdrop panes can be accessed by clicking the middle tab in between the "code" tab and the "sounds" tab. This is where we can create and manipulate sprites and backdrops. To switch between costume and backdrop panes, select the desired thumbnail in the sprite info pane.


© Adafruit Industries Page 13 of 28

The Sounds Pane




The last tab in the top left area of the interface allows us to crate and manipulate sounds. You can even record your own!

Toolbar and Tutorials



The toolbar on the top of the screen allows us to load and save projects as well as undo the deletion of sprites.



Find a variety of tutorials on how to do just about anything in Scratch by clicking the "tutorials" button!


© Adafruit Industries Page 14 of 28

Tips and Tricks

Workflow and mistakes

- Copy and paste code blocks to save time.
- Be careful when creating and deleting sprites! The code blocks you create tell the associated sprite what to do. Thus when you delete a sprite you are deleting the code that tells it what to do.

Deleting a sprite will delete all the code associated with that sprite!



If you accidentally delete a sprite, click edit on the tool bar then click "Restore Sprite" to bring your code back to life!

Troubleshooting

- Right click a block for help.
- Visit the Scratch wiki () for more help.
- There's a whole community of <u>Scratchers</u> () that have come across a multitude of issues and would also love to help.
- To join the community make an account!

What's New in Scratch 3?

Scratch 3.0 includes a new sound editor, new sprites, new programming blocks, and much more.

© Adafruit Industries Page 15 of 28

A new build

Scratch was originally built with Adobe Flash which is going away soon so the new update is built in HTML5 () and a Javascript library called React ().

What does that mean for us?

Scratch can now be used on tablets and almost all hardware, like Raspberry Pi for example!

Scratch Extensions


Scratch extensions is a new feature that allows for Scratch programs to talk to external hardware and online resources. Micro:bit () even has its own extension!

Other updates per the Scratch Wiki ():

- Stage is moved to the top right.
- New modern look and design.
- Some color changes to blocks. Events Blocks are the color of the Scratch 2.0 Control Blocks, and control blocks are a bit lighter than the old events blocks
- More Blocks has been renamed My Blocks (), and is a shade of light red
- Some default inputs (the inputs that show up in the <u>Block Palette</u> () ar e different)
- New Paint Editor () and Sound Editor ()
- Pen (), Video Sensing (), and Music () blocks are now extensions
- You can now make and play projects on tablets and play them on phones, but currently you cannot edit projects on mobile phones
- Several extra options for the "touching ()?" boolean, including "any edge", "mouse-position", and "left edge"
- Different fonts: Sans Serif (thin Helvetica), Serif (Times), Handwriting, Marker, Curly, Pixel, Chinese, Japanese, and Korean
- The vector paint editor is now the default editor
- The Video Sensing blocks are in an extension
- New extensions: <u>Text to Speech</u> (), <u>Translate</u> (), <u>Micro:bit</u> (), and Lego Mindstorms EV3.
- Internet Explorer will not be a supported browser

© Adafruit Industries Page 16 of 28

- PicoBoard () and LEGO WeDo () 1.0 are not supported
- The addition of a pause button like in Phosphorus () and Sulfurous ()
- New blocks!! (below) <u>Click here</u> () to learn more about the functionality of these blocks.




Draw Demo!

In this demo we will create a simple draw program in Scratch.

Next we will create a program in <u>MakeCode</u> () that will allow a Circuit Playground Express (CPX) to control the mouse and keyboard functions that we define in Scratch.

Lastly we create a masterpiece!



The best way to learn a new language is to start making with it, so let's go!

© Adafruit Industries Page 17 of 28

Scratch Code

Find the Scratch code to this project below. Feel free to follow along or access the code for yourself!

Click here to access the Scratch code for this project


After clicking the link above, you'll be taken to the project page. Once there, click see inside to access the code.


```
when it distributed to the color ground of the
```


Create a sprite for the pen


The first thing we want to do is make a new sprite for our pen. This sprite will not only be the visual representation of our painting tool but it will also hold all the associated code.

© Adafruit Industries Page 18 of 28









In the sprite info pane, delete any current sprites.

Next, to create a new sprite, hover the mouse over the cat with a plus sign. Now find and click the paint brush icon.

This will bring us to the sprite costume pane where we can create our very own sprite!


Our pen sprite is simple but feel free to make it extra fun.


Click the circle shape in the toolbar on the left, next disable the outline, lastly we choose the color we want for the sprite in the fill drop down. Then click and drag a small circle or whatever shape we want in the canvas.

Now we see our new sprite in the sprite info pane, so let's go ahead and name it. The last step is to change the size of the sprite by typing in the desired size in the sprite info pane.

© Adafruit Industries Page 19 of 28

Adding the pen extension blocks





In order to access the pen blocks in scratch, we need to grab the extension.


Click the extension icon on the bottom left of the blocks palette.

Next click the pen extension to add it.

© Adafruit Industries Page 20 of 28

Setting up the program





The first thing we want to do is tell the program to start after the green flag is clicked.

Next we create a variable called stepSize and set it to 3. This variable will determine how fast we want the pen to follow the mouse. Then create another variable called color_counter and set this to 0. This will help us switch colors more easily.


Next set the pen size to 5. This is the thickness of the pen.

Then we tell the pen to start in the middle of the screen at 0, 0.

Lastly we want to erase everything that's currently on the stage before the forever loop begins.

© Adafruit Industries Page 21 of 28

Forever loop




In a forever loop, we add a point towards mouse-pointer block.

Next, goes a pen down block.

Then drag a move x steps block, dragging in the variable stepSize from the variables blocks in place of the number.

Now we create a series of if statements that check for the <code>color-counter</code> value which will tell the program when to switch colors and what color to switch to.

Each time the character c is typed on the keyboard, the value of <code>color-counter</code> increases by 1 (we will get to this next). However, with the last if statement, when the value reaches above 6, it is reset back to 1.



The last few blocks of code define functions for pressing keys e (erase) and c (color).


When e is pressed, we erase the board. In the next section, when we code the CPX, we tell it to send the character e when it is shaken.

When c is pressed we increase the value of color-counter by 1. Later this will get translated into: when button A is pressed on the CPX, send the character c.

Test it out!

Now that the Scratch program is finished, test out the code in the stage by clicking the green flag to start. Move the mouse around to guide the pen. Press c to change colors and e to erase the board.


© Adafruit Industries Page 22 of 28



CPX and MakeCode

What is Circuit Playground Express (CPX)?

The Circuit Playground Express is an easy way to get started learning electronics and coding. It's filled with tons of fun lights and sensors! The CPX is what we'll use to control the mouse and keyboard to draw in our new Scratch program. Head here () to learn more about the CPX.



© Adafruit Industries Page 23 of 28

What is MakeCode?

MakeCode is a web-based code editor for physical computing made by Microsoft.

It is almost identical to Scratch in design, however it is mainly for programming hardware like the CPX rather than a sprite on a computer screen.

More on MakeCode for Adafruit boards here ().

Create a New Project with MakeCode

Head over to https://makecode.adafruit.com/ () and create a new project.

Click the button below to access the code for this project.

Click here to open the project up in MakeCode



Add the Keyboard and Mouse Extensions in MakeCode

Follow this guide () on how to add these extensions to MakeCode. They will allow us to use the CPX to act as a mouse and a keyboard!

© Adafruit Industries Page 24 of 28



The NeoPixel Palette



In an on start loop, set the colors of the NeoPixels on the CPX to the according colors. This is so the user knows which colors they have to choose from.

Coding with the accelerometer

1 G (one gee) is equivalent to Earth's gravitational pull at a resting point.

The CPX's accelerometer senses the gravity it feels in any given direction on the x, y or z axis. The value it senses is anywhere from 0 to 1023 mg (miligravities). 1G = 1000 miligravities.

Learn more about the accelerometer on the Circuit Playground Express here ().

© Adafruit Industries Page 25 of 28

```
forever

if acceleration (mg) y 

relation (mg) y 

relation (mg) y 

relation (mg) x 

relation (mg) x 

relation (mg) y 

relation (mg) y 

relation (mg) y 


relation (mg) x 

relation (mg)
```

In a **forever** loop, we create an **if else** statement that describes how the mouse should move when the CPX is tilted forwards, to the right, backwards, or to the left.

If the accelerometer senses any more that 500mg in any direction, the mouse will move in that direction.

Sending keyboard info



When button A is clicked, the CPX sends the character c for color change.

When the CPX is shaken, the CPX sends the character e for erase.

Uploading the Code

Now that we have the code for the project, we need to upload it to the CPX.

Let's name our file and download it.

- Choose a name at the bottom of the page.
- Then click the pink Download button.

Follow the directions and connect your CPX to your computer via the USB cable. Click the CPX Reset button once to go into programming mode (all the Circuit Playground Expresses' LED light NeoPixels will turn green).

In some cases, you may need to press the reset button twice to get into programming mode.

© Adafruit Industries Page 26 of 28

Next, look for the file in your downloads folder and drag it onto your CPLAYBOOT driv e that should have showed up in your file manager/finder when you plugged in your board and entered programming mode.


Once your code file is placed on the CPLAYBOOT drive should see the CPLAYBOOT drive disappear indicating the code is running.

Putting it All Together

The code should now be running! Try tilting around the CPX and see if the mouse moves.

Head to our Scratch program, enter full screen and test it out!

- Tilting the CPX moves around the pen.
- Clicking button A on the CPX changes colors.
- Shaking the CPX erases the picture.



Troubleshooting

- If the pen in scratch is acting glitchy as you tilt the CPX around, try decreasing the value of stepSize.
- Head here () to troubleshoot MakeCode issues.
- For CPX related issues head here ().
- Head to the Scratch Wiki () to troubleshoot Scratch related issues.

© Adafruit Industries Page 27 of 28

What will you create next?

How can you modify what we created to make something even cooler? What other sensors on the CPX could we use to add more effects with the pen in Scratch?

Happy Hacking!

© Adafruit Industries Page 28 of 28