
MAYWOOD STUDIO

HERITAGE QUILT



Heritage Woolies Flannel Collection by Bonnie Sullivan 68" x 78" finished quilt Confident Beginner



MAYWOOD STUDIO



by Bonnie Sullivan



Fabric 1 MASF9426-G



Fabric 2 MASF9423-T



Fabric 3 MASF9422-S



Fabric 4 MASF9424-O



Fabric 5 MASF9425-B



Fabric 6 MASF9422-Q



Fabric 7 MASF9426-A



Fabric 8 MASF9422-N



Fabric 9 MASF9423-R



Fabric 10 MASF9422-O



Fabric 11 MASF9424-K



Fabric 12 MASF9424-R



Fabric 13 MASF9422-K




Fabric 14 MASF9424-K2



Fabric 15 MASF9424-S



Fabric 16 MASF9421-K



FABRIC 17 MASF9425-KJ



Fabric Requirements		
Fabric 1	MASF9426-G	1/4 yd
Fabric 2	MASF9423-T	1/4 yd
Fabric 3	MASF9422-S	1/4 yd
Fabric 4	MASF9424-O	1/4 yd
Fabric 5	MASF9425-B	1/4 yd
Fabric 6	MASF9422-Q	1/3 yd
Fabric 7	MASF9426-A	1/3 yd
Fabric 8	MASF9422-N	1/3 yd
Fabric 9	MASF9423-R	1/3 yd
Fabric 10	MASF9422-O	1/3 yd
Fabric 11	MASF9424-K	1/4 yd
Fabric 12	MASF9424-R	1/4 yd
Fabric 13	MASF9422-K	1/4 yd
Fabric 14	MASF9424-K2	1-3/4 yds
Fabric 15	MASF9424-S	1/4 yd
Fabric 16	MASF9421-K	3/4 yd
Fabric 17 Binding	MASF9425-KJ	2/3 yd
Backing	your choice	4-1/4 yds



Finished Size 68" x 78"

Cutting

Fabrics 1-2-3-4-5

A - cut (1) 6-1/2" WOF strip

Fabrics 6-7-8-9-10

B- cut (1) 6-1/2" x WOF strip C- cut (2) 2-1/2" x WOF strips

Fabrics 11-12-13-14-15

D- cut (2) 2-1/2" x WOF strips

Fabric 14: Outer Borders

cut (8) 6-1/2" x WOF strips

Fabric 16: Inner Border

cut (6) 3-1/2" x WOF strip

Fabric 17: Binding - Cut (8) 2-1/2" x WOF strips

WOF = Width of Fabric




Block: 10-1/2" x 10-1/2" 10" square finished make 6 of each

Heritage Woolies Flannel Quilt


Please read all instructions before you begin. Seam allowance is 1/4" unless otherwise stated. Press in the directions of arrows. Use a walking foot or dual feed when sewing with flannel. Do not pre-wash.

Block Assembly


- 1. Sew a (Fabric 11) D strip to either side of a (Fabric 6) B strip, right sides together. Press.
- 2. Subcut into (12) 2-1/2" x 10-1/2" pieces.




- 3. Sew a (Fabric 6) C strip to either side of a (Fabric 1) A strip, right sides together. Press.
- 4. Subcut into (6) 6-1/2"_x 10-1/2" pieces





5. Sew a strip set 1 piece to either side of a strip set 2 section, nesting the seams, right sides together. Make 6.





6. Repeat steps 1 - 5 to make Blocks B, C, D, E.












Row Assembly

7. Sew the blocks into 6 rows of 5 blocks following the diagram below. Press rows in opposite directions. Sew row to row. Press rows open.



8. Inner Side Borders: Measure the length of the quilt through the middle:______ Piece together 3 (Fabric 16) border strips and trim to make 2 border strips that equal the measurement. Sew to the sides of the quilt. Press away from center.

9. Inner Top and Bottom Borders: Measure the width of the quilt through the middle:_______
Piece together 3 (Fabric 16) border strips and trim to make 2 border strips that equal the measurement.
Sew to the top and bottom of the quilt. Press away from center.

10. Outer Side Borders: Measure the length of the quilt through the middle:

Piece together 2 (Fabric 14) border strips and trim to make a border strip that equals the measurement.

Repeat with the remaining 2 strips to make a second border strip of the same size. Sew to the top and bottom of the quilt. Press toward center.

11. Outer Top and Bottom Borders: Measure the width of the quilt through the middle:_______
Piece together 2 (Fabric 14) border strips and trim to make a border strip that equals the measurement.
Repeat with the remaining 2 strips to make a second border of the same size. Sew to the top and bottom of the quilt. Press toward from center.



- 12. Layer the backing (wrong side up), batting and quilt top (right side up). Baste layers to secure. Quilt as desired.
- 13. Sew the binding strips together into one continuous strip. Press in half length-wise. Sew the binding to the quilt top with a 3/8" seam allowance, mitering the corners. Trim the excess backing and batting, then turn the binding to the back side of the quilt and stitch down by hand with matching thread.

