



Installation Guide

PowerDesigner® 16.1

Windows

DOCUMENT ID: DC38092-01-1610-01

LAST REVISED: November 2011

Copyright © 2011 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. A ® indicates registration in the United States of America.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names used herein may be trademarks or registered trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568

Contents

CHAPTER 1: Planning Your PowerDesigner	
Installation	1
Obtaining a License Key File	3
Installing a License Server	4
Adding Additional Licenses with Imtools	7
Troubleshooting with Imutil	7
SySAM for IPv6 Environments	8
SySAM for 64-Bit and Non-Windows Environments	8
Upgrading PowerDesigner	8
Windows 64-Bit Support	9
Password and Data Encryption	9
CHAPTER 2: Installing PowerDesigner	11
Installing PowerDesigner in Administrative Mode	15
Creating the Administrative Install on the Server	16
Installing Client Machines	16
Upgrading an Administrative Install	17
Installing PowerDesigner in Silent Mode	17
Uninstalling PowerDesigner in Silent mode	18
Uninstalling PowerDesigner and Installation	
Maintenance	19
Manual Fonts Installation	20
PowerDesigner Dependencies	20
CHAPTER 3: Installing the Repository	21
Installing and Authenticating SQL Anywhere	22
Creating a Database to Contain the Repository	23
Installing the Repository to the Server	24

- Creating a Data Source to Access Your Database26
- Troubleshooting the Repository Installed on ASE28
- Troubleshooting the Repository Installed on DB229
- Troubleshooting the Repository Installed on SQL
Server29
- Installing the Repository Proxy29**
- Installing the PowerDesigner Portal Server31**
 - Accessing the PowerDesigner Portal Web Site36
 - PowerDesigner Portal Security37
 - Installing the PowerDesigner Portal Server on UNIX39
 - Multiple PowerDesigner Portal Instances on One
Server40
 - Changing the Repository DBMS41
- Upgrading the Repository41**
 - Post-Upgrade Cleanup for a Repository Containing
Branches42
- Deleting the Repository43**

- Index45

Planning Your PowerDesigner Installation

The deployment of PowerDesigner® typically involves the installation of a license server, a repository, and a number of client machines.

Note: For installation of PowerDesigner without a repository, complete steps one and two of this procedure and then go directly to *Chapter 2, Installing PowerDesigner* on page 11.

1. Obtain your license key file (see *Obtaining a License Key File* on page 3).
If you do not have a license key, you will only be able to install PowerDesigner for a 15-day trial period.
2. Install the Sysam license server (see *Installing a License Server* on page 4).
The license server is required if you intend to share served licenses among users instead of assigning individual licenses per machine.
3. Install PowerDesigner on the administrator's workstation (see *Chapter 2, Installing PowerDesigner* on page 11).
This initial installation is needed to install the PowerDesigner repository, which is used to store and share models.
4. Choose a server capable of supporting large, long-running transactions to host your repository. We recommend as a minimum, a dual-core machine, with 2-4GB of RAM, but the exact system requirements depend on your DBMS, the number of concurrent users, and the size of your repository.

Note: To calculate the size required for your repository database, estimate the number of models that will be stored and the period during which they will be developed. An average model containing 100 primary objects (tables, classes, etc.) will have an initial disk size of 5MB and the size of its initial check in will be around 10MB. Assuming an average number of edits, each subsequent check in will add 10% to the size of the file, so that after an average development period of two months (40 working days) with one check in per day, the final model file size will be $10\text{MB} * 1.1^{40}$ or approximately 500MB. If your team will develop 20 such models during the course of the year, you should allow 10GB of space for your repository database.

If you want to use the repository proxy or PowerDesigner Portal, you should install them, by preference, on the same machine where the repository is located to optimize communication between the components. If the repository server is not a Windows server or is unable to support the additional workload, then we recommend installing these components on another machine on the same LAN segment.

5. Install SQL Anywhere® on the repository server and create a database to house the PowerDesigner repository (see *Installing and Authenticating SQL Anywhere* on page 22) .

Alternatively, create a database to house the repository in one of the other supported DBMSs:

- Adaptive Server® Enterprise
- Oracle 8 and higher
- IBM DB2 Common Server and DB2 for OS/390
- Informix 2000
- Microsoft SQL Server 2005 and higher - we recommend that you use a server that is not currently managing a high transaction load, since PowerDesigner performs long- running synchronous transactions during Check-In/Check-Out.

Note: The most up-to-date list of supported DBMSs, is available at <http://certification.sybase.com>.

6. Install the repository to the new database (see *Installing the Repository to the Server* on page 24).
7. [optional] Install the repository proxy on the repository server (see *Installing the Repository Proxy* on page 29).

The proxy simplifies and offers more security for connection to your repository and may provide performance improvements in environments where clients will be connecting over a WAN or complicated LAN or when dealing regularly with large (15MB+) models.

8. [optional] Install the PowerDesigner Portal on the repository server (see *Installing the PowerDesigner Portal Server* on page 31).

The PowerDesigner Portal provides access to your repository models via a Web browser.

9. Specify your password policy, optionally connect PowerDesigner to an SMTP server, and create user accounts and groups with appropriate rights and permissions to allow users to connect to the repository (see *Core Features Guide > Administering PowerDesigner > Controlling Repository Access*).

Note: The repository can be configured to delegate the authentication of repository users to an LDAP server (see *Core Features Guide > Administering PowerDesigner > Controlling Repository Access > Controlling Repository Access with LDAP*).

10. [optional] Customize the PowerDesigner interface to optimize it for various groups of users and define shared reference models and resources:
 - Prepare profiles to customize the PowerDesigner interface (by hiding types of models, objects, and properties and customizing menus, toolbars, and settings) and associate them with appropriate users and groups (see *Core Features Guide > Administering PowerDesigner > Customizing the PowerDesigner Interface*).

- Prepare shared reference models and an enterprise glossary for deployment to users (see *Core Features Guide > Administering PowerDesigner > Deploying an Enterprise Glossary and Library*).
 - Prepare custom resource files (such as DBMSs, languages, and extensions) for deployment to users (see *Core Features Guide > Administering PowerDesigner > Deploying an Enterprise Glossary and Library > Deploying an Enterprise Library > Sharing Resource Files via the Library*).
- 11.** Install PowerDesigner on user machines (see *Chapter 2, Installing PowerDesigner* on page 11).

Note: If you are not using the repository proxy, you will also need to install the SQL Anywhere client (as part of the PowerDesigner installation) or an appropriate client or driver for your chosen DBMS on all client machines to allow them to connect to the repository.

Obtaining a License Key File

You must have a *license key file* to install PowerDesigner. License files can be downloaded on the Sybase® Product Download Center site (SPDC) at <https://sybase.subscribenet.com/>.

- When you purchase PowerDesigner from Sybase, you receive an E-mail with an URL, your login, and your password for the SPDC.
- When you purchase PowerDesigner from a Sybase reseller, you receive a certificate with a Web key registration number and a download URL.

Host ID

Before accessing the download site, make sure you know your license configuration, the *host ID* and the *name of the computer* that will receive the license key file. You can find the host ID and the computer name in the Installation program, these details are automatically calculated and displayed in the third page of the installation where you are asked to load or copy a license file to proceed.

For Windows platforms, if your machine does not have a network adapter an alternate Hostid of type Disk Serial Number is supported. To get this host id, use the "lmutil lmhostid -vsn" command or get the disk's volume serial number by executing "DIR C:", remove "-" from the value and prefix "DISK_SERIAL_NUM=" to the serial number to get the host id.

Each host ID type has valid formats that will be checked when generating a license. Make sure the value entered matches these valid formats.

Ethernet addresses are 12 character hex values consisting of digits 0 through 9 and characters A through F. They may be entered in any of the following formats:

- 12AB34CD56EF
- 12-AB-34-CD-56-EF

CHAPTER 1: Planning Your PowerDesigner Installation

- 12:AB:34:CD:56:EF

Host Ids are 8 character hex values consisting of digits 0 through 9 and characters A through F. They may be entered in the following formats:

- 12AB34CD
- 12AB-34CD

Note: For some platforms, host IDs can also be entered in decimal formats, in this case prefix the host id with a "#" sign. Example: #1039716963

Disk Serial Number is always entered with a "DISK_SERIAL_NUM=" prefix. For example: DISK_SERIAL_NUM=3e2e17fd

Installing a License Server

If you intend to use standalone served or floating served licenses, you must either install the SySAM license server provided as part of the PowerDesigner installation or locate an existing SySAM license server on your network, to which your PowerDesigner licenses can be assigned.


The license server serves a license to a user upon request and retrieves it when it is no longer being used. If all the licenses are already in use, the license server informs you that no license is available.

You must already have obtained a license file before you can install the license server (see *Obtaining a License Key File* on page 3).


Note: Do not install a license server and PowerDesigner on the same workstation. License servers installed with PowerDesigner v11 are not compatible with v12.0 and higher. If you no longer use PowerDesigner v11, we recommend that you uninstall the old license server.

If you borrow a mobile license and your workstation has installed other products with Flexlm served licenses, you may encounter problems returning your license to the server.

1. Select the machine on which you want to install the SySAM license server (this should not be a workstation on which you will install any Sybase product), and insert the PowerDesigner CD.
2. Click the **Install Licenses Server** button to open the Sybase Software Asset Management Installshield wizard:



3. Click **Next** to display the license agreement page. Read the License Agreement and click the **I Agree** radio button to accept the terms of the agreement. If you click **I Do Not Agree**, the installation will be cancelled.
4. Click **Next** to display the license file definition page and perform one of the following actions:
 - If you already have a license file, click the **Load** button and browse to the folder where your license file is located. The content of the license file is automatically displayed in the License key box.
 - Download a license file from SPDC and copy the file content into the License Key box.



5. Click **Next**.

The destination folder page is displayed if no other SySAM license server is detected on the machine.

6. Select the suggested installation directory or browse to a new one and then click **Next** to go to the settings page.

7. Click **Next** to accept the current settings and start copying files.

The copy starts. A progress box is displayed and Setup copies files to the destination directory. When installation is complete:

- If SySAM had to be installed, you can choose to start the license server as a service.
- If the PowerDesigner licenses were assigned to an existing license server, you can choose to reread the licenses to refresh the server license file.

8. Click **Finish** to exit the wizard.

Note: If a firewall is activated on the computer where the license server is installed, then the ports 27000 and 27010 must be opened in the firewall. For a Windows Firewall, you may need to add the port 27000 and the SySAM executable (for example C:\Sybase\SYSTEM-2_1\Bin\SYBASE.exe to the list of exceptions.


Additionally, on Windows and UNIX platforms, edit the license server license files to add the port number 27000 to the line beginning SERVER and add a new line VENDOR SYBASE PORT=27010 directly after it. When you have finished, these lines should read as follows:

```
SERVER server_name server_id 27000
VENDOR SYBASE PORT=27010
```

Adding Additional Licenses with Imtools

The license server should configure itself correctly at installation. If you need to subsequently add additional licenses or otherwise administer the server, you can do so using `Imtools.exe`

1. Double-click **SYSAM-x_x\Bin\Imtools.exe** to open the LMTOOLS dialog.
2. On the **Service/License File** tab, select **SYSAM** in the list of servers:



3. Click the **Start/Stop/Reread** tab and click the **Reread License File** button to force the server to read again the file `sybpdcs.lic` and update license number.
4. Select **File > Exit** to close the LMTOOLS dialog.

For detailed information about `Imtools`, follow the SySAM Documentation Collection link available at <http://www.sybase.com/sysam>.

Troubleshooting with Imutil

`Imutil.exe`, which is available in the `SYSAM-x_x\Bin` folder provides various diagnostic possibilities.

For example, the following command can be used to find the user(s) who have currently borrowed the license(s):

```
lmutil lmstat -a -c <port>@<host> where <port> and <host> are license server information.
```

CHAPTER 1: Planning Your PowerDesigner Installation

For detailed information about lmutil, follow the SySAM Documentation Collection link available at <http://www.sybase.com/sysam>.

SySAM for IPv6 Environments

By default, the 32-bit Windows version of SySAM for IPv4 is provided in the PowerDesigner setup. You can add IPv6 support easily after installation by copying the appropriate executables in the installation directory.

1. Open `SYSAM-x_x\Bin\lmttools.exe` and click the **Start/Stop/Reread** tab.
2. Select the `SYSAM` server in the list and click **Stop Server** (you may need to select the **Force Server Shutdown** check box if licenses are currently being borrowed).
3. Open the folder `SYSAM-x_x\Bin\binIPv6`, and copy the files `lmgrd.exe` and `SYBASE.exe` to `SYSAM-x_x\Bin`, overwriting the existing versions.
4. Return to the **Start/Stop/Reread** tab in the `LMTOOLS` dialog, and click **Start Server**.

SySAM for 64-Bit and Non-Windows Environments

You can obtain a SySAM server for 64-bit Windows or for a non-Windows environment from the Sybase website.

Note: The 32-bit version of SySAM will run on a 64-bit Windows machine, but if you prefer to install a 64-bit version, you can download it from the Sybase website.

To download a 64-bit version of SySAM for Windows or a SySAM server for a non-Windows environment, go to <http://www.sybase.com/sysam>, select **SySAM Standalone License Servers**, and follow the download instructions.

Note: Any licenses that have been activated for a Windows server must be reactivated for any other platform.

Upgrading PowerDesigner

This topic provides guidance on issues relating to Office add-ins, the license server, and resource files, which may arise when upgrading PowerDesigner.

- Repository branches - Prior to v16.1, the repository browser only supported displaying a single branch at a time. When you upgrade an existing repository to v16.1, all branches will become, by default, visible for all users. You may wish to simplify viewing the repository by deleting documents and branches that are no longer used, by using permissions to hide certain branches from users or groups who have no need of them, or by migrating active models to a new repository (see *Post-Upgrade Cleanup for a Repository Containing Branches* on page 42).

- Office add-ins - Though PowerDesigner v15.x and v16.x can be installed together on the same workstation, after the installation of v16.x, the add-ins supporting importing from MS Word and Visio will only function for v16.x.
- License Server - In general, you can serve licenses for clients using PowerDesigner v15.x and v16.x from the same SySAM license server. However, if you want to support heterogeneous versions of the Data Architect package (which is only available as an upgrade to v16.x and not as a new purchase), you will need to install a second license server on another machine and plan to serve the licenses associated with each version from a separate server.
- Resource Files - DBMS and language definition files and other resource files provided with PowerDesigner are constantly evolving. If you have not edited the resource files delivered with a previous version of PowerDesigner, then the upgrade to the latest version will happen silently.

If you have edited a definition file or other resource file from a previous version, then it will continue to work with the new version. However, we advise you to use the **Compare** tool to review the differences between your file and the file delivered with the new version and, if appropriate, merge them to obtain bug fixes or new features. For information about comparing and merging resource files, see *Customizing and Extending PowerDesigner > PowerDesigner Resource Files*.

If you have stored resource files from a previous version in the repository then you must check them in again under the new version before you can continue to use them. Resource files can now be stored in the library and pushed to users (see *Core Features Guide > Administering PowerDesigner > Deploying an Enterprise Glossary and Library > Deploying an Enterprise Library > Sharing Resource Files via the Library*).

Windows 64-Bit Support

PowerDesigner is only available in a 32-bit version, but installation on 64-bit versions of Windows is supported.

To ensure that PowerDesigner can communicate with your data sources, you should use the 32-bit version of the ODBC Administrator tool. PowerDesigner cannot connect to 64-bit ODBC DSNs. For detailed information about working with 32-bit DSNs on a 64-bit version of Windows, see <http://support.microsoft.com/kb/942976>.

Password and Data Encryption

PowerDesigner supports encryption of both passwords and data for direct and proxy connections to a repository and for connections to other databases using most of the supported DBMSs via one or more of native, ODBC, and JDBC connection profiles.

The following table provides information and examples for encrypting passwords and data with each type of connection:

Type	Encryption
Native	<p>Password and data encryption can generally be enabled with connection parameters.</p> <p>For example, the password for Sybase Adaptive Server Enterprise is encrypted by default, and you can enable data encryption by setting the <code>Sec_Confidential</code> connection parameter to 1.</p>
ODBC	<p>Password and data encryption can generally be enabled in the ODBC Configuration dialog.</p> <p>For example, to encrypt the password for Sybase SQL Anywhere, select the Encrypt password option on the Login tab, and to encrypt data, select an encryption method on the Network tab.</p>
JDBC	<p>It is not possible to control password and data encryption through the PowerDesigner connection profile interface, but you may be able to enable encryption directly in your database client.</p>

For more information about using PowerDesigner connection profiles, see *Core Features Guide > The PowerDesigner Interface > Getting Started > Connecting to a Database*. For detailed information about encryption and other parameters for your database, see your DBMS documentation.

You can install PowerDesigner directly on individual client machines, including as a plugin for the Eclipse and Visual Studio IDEs. You can also perform a mass silent installation or an administrative installation to a network server.

Note: You should obtain a license key (see *Obtaining a License Key File* on page 3) and, if appropriate, install and configure your license server (see *Installing a License Server* on page 4) before beginning.

PowerDesigner has the following minimum system requirements:

- Microsoft Windows XP, Vista, or 7 or Microsoft Windows Server 2003 or 2008
- 1.5 GHz processor
- 1 GB RAM (2 GB recommended)
- SVGA or higher-resolution graphics adapter and compatible color monitor (800x600)
- CD-ROM drive
- 1GB disk space for installation of all the core modules (and demonstration videos).

For information about the frameworks and libraries and frameworks required by PowerDesigner, see *PowerDesigner Dependencies* on page 20.

Note: Non-Administrator users may receive a warning message during installation as setup requires write access on certain directories and on the registry that they may not have. Setup can go on despite this message.

1. Insert the PowerDesigner CD-ROM in your drive.

If setup does not automatically start, then double-click the SETUP.EXE file in the setup directory of the CD-ROM.

2. Click the **Install PowerDesigner 16.1** button to open the welcome page, and then click **Next** to go to the license selection page.

3. Select one of the following license types:

- *Trial version* – is a full-featured version, valid for an evaluation period of 15 days, that allows you to perform any design task. Contact Sybase if you require a limited extension.
- *Local standalone license* – is installed on and locked to a particular machine. Click **Next** to go to the license key page, where you must load a valid license file (see *Obtaining a License Key File* on page 3).
- *Served standalone license* – is provided by one or more SySAM license servers, and is locked to a particular machine. Click **Next** to go to the license server page, where you must enter the name of your license server.

CHAPTER 2: Installing PowerDesigner

- *Served floating license* – is provided by one or more SySAM license servers, which manage the allocation and recuperation of licenses among a pool of users. Click **Next** to go to the license server page, where you must enter the name of your license server.

For more information about PowerDesigner licensing, see *Core Features Guide > The PowerDesigner Interface > Getting Started > License Management*.


4. [for served licenses] Click **Next** to go to the package selection page, where you can select which package to install. The list displays all the packages that are available on the server but it does not necessarily reflect the current availability of a license for a particular package.
5. Click **Next** to go to the license agreement page. Select the location where you are installing the software, read the License Agreement, and then click the **I Agree** radio button to accept the terms of the agreement. If you click **I Do Not Agree**, you cannot proceed with the Setup program.

Note: You can print the License Agreement from the Setup\Licenses directory on the product CD.

6. Click **Next** to go to the directory selection page. Accept the default installation directory or choose another by clicking the **Browse** button.

We recommend that you do not install a new major version of PowerDesigner in a directory that holds a previous version.

7. Click **Next** to go to the component selection page, which lists the products and features that are available to install. Each node can be expanded in order to let you select or deselect sub-features:

**Note:**

- The PowerDesigner plugin for Eclipse is available for Eclipse v3.2 to v3.6. For more information, see *Core Features Guide > The PowerDesigner Interface > The PowerDesigner Plugin for Eclipse*.
- The PowerDesigner add-in for Microsoft Visual Studio and Team Foundation is available for Visual Studio 2005, 2008, and 2010. For more information, see *Core Features Guide > The PowerDesigner Interface > The PowerDesigner Add-In for Visual Studio*.
- The SQL Anywhere drivers provide connectivity to a repository installed on SQL Anywhere, which is bundled with PowerDesigner (see *Installing and Authenticating SQL Anywhere* on page 22).
- Addins for third-party software such as MS Word and Visio are not selected by default for installation. If you want to install these addins, expand the General Addins node, and select them for installation.

Select or clear check boxes as necessary, and then click **Next**.


8. If you selected the Eclipse 3 plug-in in the list of components, the Eclipse directory selection page is displayed. Click the **Browse** button to specify a directory containing a valid Eclipse installation.

Note: If you had manually installed the Eclipse plug-in in PowerDesigner version 10 or 11 and want to upgrade to version 16.x you have to remove the plug-in manually. To do so,

open the Eclipse directory, and remove any PowerDesigner-related folder under the `\configuration`, `\features`, and `\workspace\metadata\plugins` folders.


9. Click **Next** to go to the user profiles page. Select the user profiles that you want to apply immediately to your installation.

Note that whatever you select on this page, all the profiles will be installed and you can apply any profiles after installation. If you select two or more contradictory profiles (for example, E/R Notation and Barker Notation, in the CDM category), the one that appears last in the list will be applied:



For more information about user profiles, including how to make your own profiles available to the installer, see *Core Features Guide > The PowerDesigner Interface > Customizing Your Modeling Environment > User Profiles*.

10. Click **Next** to go to the program folders page. You can select to make PowerDesigner available from the default folder or select or create another.
11. Click **Next** to go to the current settings page, which lists all your selections. Select the **Keep PowerDesigner Settings** check box to retain any settings from a previous version of PowerDesigner.



12. Click **Next** to begin the install. Setup begins copying files to the destination directory.
13. Wait for the setup to complete, and then click **Finish** to exit the wizard. Depending on your working environment, you may be prompted to reboot your machine.

Note: The `Readme.html` file, which contains important release information, is available in the root of your installation directory.

Installing PowerDesigner in Administrative Mode

System administrators can install PowerDesigner on a server and have client machines run the application from this central install. The client machines do not install any files but their registry is modified in order to be able to access PowerDesigner from the specified location.

With this type of administrative mode install, there is only one instance of PowerDesigner to deploy and upgrade.

You can install any type of PowerDesigner license and specify any combination of installation options on each client machine.


Creating the Administrative Install on the Server

The first part of the administrative install consists in copying the PowerDesigner files to a server. You are not required to enter any product key or select any feature to install. All PowerDesigner setup files are decompressed and copied to the server, but the server registry and system files will not be affected.

1. Insert the CD-ROM in the drive to automatically launch the setup program. The initial setup dialog box is displayed. Click the **Administrative Installation** button.

or

Select **Start > Run**, type the PowerDesigner setup.exe path followed by /a in the Run dialog box and click **OK**.



The welcome page is displayed.

2. Click **Next** to display the network location page.
3. Specify the network location where you want to copy the product files, and then click **Install**.

The setup status page displays a progress box while the files are copied to the destination directory. When this process is complete, the complete page opens.

4. Click **Finish** to exit the InstallShield Wizard.

Installing Client Machines

Once you have created the administrative install on the server, you can set up the client machines. The client install modifies the registry of the client machine in order to be able to reference the files located on the server, but does not copy any file onto the client machine. Consequently no space is required on the client machine.

1. On the client machine, open Windows Explorer, connect to the network location where you have created the administrative install and double-click the Setup.exe file.

The welcome page is displayed.

2. Click **Next** to open the license selection page, select a license type, and then click **Next** again.

3. Define the appropriate installation parameters on the following pages, and then click Finish to begin the install.

Depending on your working environment, Setup may ask you to reboot your machine.

Upgrading an Administrative Install

You can pass the administrative install command to an upgrade package downloaded from the web.

Note: You cannot upgrade between major versions. Each major version (12.x, 15.x, etc.) must be installed as a new administrative install in its own directory.

Use the following syntax to upgrade your administrative install to a new minor version:

```
upgrade_package.exe /a
```

Installing PowerDesigner in Silent Mode

If you need to deploy PowerDesigner on a large number of machines and wish to reuse *exactly* the same setup options and destination folder for each machine, you can use the silent install mode. Silent install runs without user input, by using a *response file* (called *setup.iss*) that specifies all the required installation options.

The silent installation mode does not provide any information about the installation itself. You can open the setup.log file in the directory containing the setup.exe file to have a report about the silent install. The last section of this ResponseResult file contains a line ResultCode=X. If X=0, installation was successful.

Note: You can perform a silent install from the product CD or from a network location where the PowerDesigner installation files have been copied (see *Creating the Administrative Install on the Server* on page 16).

1. To create a setup.iss response file, select **Start > Run** to open the Windows Run dialog box and enter the following command:

```
<PD-inst-dir>\setup\setup.exe /r /f1 "<path>\setup.iss"
```

Complete the installation parameters as required and then click Finish to create the setup.iss file at <path>. For example, the following:

```
G:\setup\setup.exe /r /f1 "setup.iss"
```

References a network drive G:, mapped to a location where the PowerDesigner files have been copied, and creates setup.iss in the setup directory for easy access.

2. Proceed to install the client machine with the following command:

```
<PD-inst-dir>\setup\setup.exe /s /f1 "<path>\setup.iss".
```

Each new silent install will replace the content of the setup.log file located in the Installation drive.

CHAPTER 2: Installing PowerDesigner

Use the /f2 parameter to define a local directory where the setup.log file will be stored on each client machine:

```
G:\setup\setup.exe /s /f2"c:\temp\setup.log"
```

Note: From a client machine, map a drive to the server where the PowerDesigner files are copied. The drive letter must be the same as that on the server. For example, if your PowerDesigner files are located on drive R:\admin\setup.exe, you must use the R drive on each client machine to access installation files.

Uninstalling PowerDesigner in Silent mode

A silent uninstall works in a similar fashion to the silent install, but requires that you locate the InstallShield PowerDesigner maintenance file.

For PowerDesigner v16.x this file is located, by default, at:

```
C:\Program Files\InstallShield Installation Information\{D88DF8F0-B749-4D26-AFBC-A6E588099793}\setup.exe
```

Note: It may be that your maintenance file is not found in the standard location. You can always retrieve its location file from the following registry key: HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\{D88DF8F0-B749-4D26-AFBC-A6E588099793}

1. To create an uninstall.iss response file, select **Start > Run** to open the Windows Run dialog box to invoke the installshield maintenance file with the following options:

```
<path-to>\setup.exe /r /f1"<path>\uninstall.iss"
```

Complete the installation parameters as required and then click Finish to create the uninstall.iss file at <path>. For example, the following:

```
C:\Program Files\InstallShield Installation Information  
\setup.exe /r /f1"C:\temp\uninstall.iss"
```


Uses the standard maintenance file, and creates uninstall.iss in a temp directory.

2. Proceed to uninstall the client machine with the following command:

```
<path-to>\setup.exe /s /f1"<path>\uninstall.iss"
```

Uninstalling PowerDesigner and Installation Maintenance

After installing PowerDesigner on your machine, you can modify the installation by selecting **Control Panel > Add/Remove Programs** or by restarting the installation.



You can:

- *Modify* - your PowerDesigner installation by adding or removing program features. Select or clear components in the components page.
- *Repair* - your PowerDesigner installation by reinstalling it. You must have the installation CD or access to the network drive where installation files are copied.
- *Remove* - your installation and clean up your registry.

Note: User files are not removed and you cannot modify your license configuration.

Manual Fonts Installation

If setup fails to define default fonts, you can do it manually.

1. Select the Fonts page in the General Options dialog box and define fonts for UI, Code and RTF Editor.
2. Create a new report, select **Report > Change Font** and define new fonts.
3. Verify that the following registry key does not exist: HKEY_CURRENT_USER\Software\Sybase\PowerDesigner 16\DisplayPreferences\Font Name.
4. Create a registry key named Font Name (with the following string values: Name, Size, Style) for all symbols in the following registry key: HKEY_LOCAL_MACHINE\Software\Sybase\PowerDesigner 16\DisplayPreferences\Font Name.

PowerDesigner Dependencies

PowerDesigner depends on a certain number of frameworks and libraries and will install them if they are not present in your environment.

- WindowsInstaller-KB893803-v2-x86.exe - to support the installation of .NET.
- Microsoft .NET Framework 4.0
- Windows Installer 3.1 and Windows Imaging Component - for your Windows version.
- o2003pia.msi, o2007pia.msi, o2010pia.msi - Microsoft Office Primary Interop Assemblies for MS Office 2003, 2007, and 2010 to support PowerDesigner MS Office plugins.
- extensibilityMSM.msi - shared Addin Extensibility update for .Net to support PowerDesigner MS Office plugins.
- msxml6-KB954459-enu-x86.exe - to support the PowerDesigner XSM.
- vjredist.exe - Microsoft Visual J# 2.0 redistribuable to support the PowerDesigner Auto-Layout feature.
- ProjectAggregator2.msi - to support the PowerDesigner Visual Studio add-in.
- vcredist_x86.exe - Microsoft Visual C++ 2010 Runtime Libraries

The PowerDesigner repository can be used to store your PowerDesigner models and other files relating to your design projects. An administrator must set up the repository, which is stored in a database on a server.

For information about using the repository, see *Core Features Guide > The PowerDesigner Interface > The Repository*.

1. Choose a server capable of supporting large, long-running transactions to host your repository. We recommend as a minimum, a dual-core machine, with 2-4GB of RAM, but the exact system requirements depend on your DBMS, the number of concurrent users, and the size of your repository.

Note: To calculate the size required for your repository database, estimate the number of models that will be stored and the period during which they will be developed. An average model containing 100 primary objects (tables, classes, etc.) will have an initial disk size of 5MB and the size of its initial check in will be around 10MB. Assuming an average number of edits, each subsequent check in will add 10% to the size of the file, so that after an average development period of two months (40 working days) with one check in per day, the final model file size will be $10\text{MB} * 1.1^{40}$ or approximately 500MB. If your team will develop 20 such models during the course of the year, you should allow 10GB of space for your repository database.

If you want to use the repository proxy or PowerDesigner Portal, you should install them, by preference, on the same machine where the repository is located to optimize communication between the components. If the repository server is not a Windows server or is unable to support the additional workload, then we recommend installing these components on another machine on the same LAN segment.

2. Install SQL Anywhere® on the repository server and create a database to house the PowerDesigner repository (see *Installing and Authenticating SQL Anywhere* on page 22) .

Alternatively, create a database to house the repository in one of the other supported DBMSs:

- Adaptive Server® Enterprise
- Oracle 8 and higher
- IBM DB2 Common Server and DB2 for OS/390
- Informix 2000
- Microsoft SQL Server 2005 and higher - we recommend that you use a server that is not currently managing a high transaction load,

CHAPTER 3: Installing the Repository

since PowerDesigner performs long- running synchronous transactions during Check-In/Check-Out.

Note: The most up-to-date list of supported DBMSs, is available at <http://certification.sybase.com>.

3. Install the repository to the new database (see *Installing the Repository to the Server* on page 24).
4. [optional] Install the repository proxy on the repository server (see *Installing the Repository Proxy* on page 29).

The proxy simplifies and offers more security for connection to your repository and may provide performance improvements in environments where clients will be connecting over a WAN or complicated LAN or when dealing regularly with large (15MB+) models.

5. [optional] Install the PowerDesigner Portal on the repository server (see *Installing the PowerDesigner Portal Server* on page 31).

The PowerDesigner Portal provides access to your repository models via a Web browser.


6. Specify your password policy, optionally connect PowerDesigner to an SMTP server, and create user accounts and groups with appropriate rights and permissions to allow users to connect to the repository (see *Core Features Guide > Administering PowerDesigner > Controlling Repository Access*).

Note: The repository can be configured to delegate the authentication of repository users to an LDAP server (see *Core Features Guide > Administering PowerDesigner > Controlling Repository Access > Controlling Repository Access with LDAP*).

Installing and Authenticating SQL Anywhere

The PowerDesigner repository is delivered with an *authenticated* version of Sybase SQL Anywhere, which can only be used to store your PowerDesigner model repository. Note that the trial version of PowerDesigner is supplied with a lighter version of SQL Anywhere, for which the setup may be slightly different.

1. Insert the software CD-ROM in the drive, and click the **Install SQL Anywhere** button. Choose your setup language, and then click **Next** to open the SQL Anywhere InstallShield wizard.
2. Click **Next** to go to the license agreement page. Select your country or region, review and accept the license terms, and then click **Next** to go to the **Custom Setup**.
3. Leave all the defaults, click **Next**, and then click **Install** to start the installation.



4. When the installation is complete, you will be invited to view the ReadMe and online resources. Make your choices, and then click **Finish** to exit the wizard
5. Copy the `authenticate.sql` file delivered in the `Setup\support` directory of the installation media (and installed to the `Tools` directory of your PowerDesigner installation) to the `\Scripts` directory in your SQL Anywhere installation on the repository server.

Copying these statements in this way ensure that when you create a database, it will automatically be authorized for use with the PowerDesigner repository.

Note: If you create a database before having copied the authentication instructions in this way, then you will need to authenticate it manually by opening the Interactive SQL tool, logging into your database, and running the contents of `authenticate.sql` against it.

Creating a Database to Contain the Repository

Once you have installed SQL Anywhere, you must create an authenticated database on the repository server to which you will deploy the repository.

1. Select **Start > Programs > SQL Anywhere 12 > Admin Tools > Sybase Central** to open Sybase Central.
2. Select **Tools > SQL Anywhere 12 > Create Database** to open the Create Database Wizard.

3. Click **Next** to go to the Select a Location page. The **Create a database on this computer** option is automatically selected. Click **Next** to go to the Specify a Database File page.
4. Enter an appropriate name and location for the database, and then click **Next** to go to the Specify the Transaction Log File page.

Note: You will need to specify this file when you create a data source to allow PowerDesigner to connect to the database (see *Creating a Data Source to Access Your Database* on page 26).

5. Make sure the **Maintain the Following Transaction Log File** check box is selected, accept or specify an alternate log file name and location, and then click **Next**.
6. Continue clicking **Next** and accepting the default settings until you arrive at the Specify DBA User and Password page.
7. By default, the database is created with an administrator account called DBA, and with a password `sql`. Select these defaults or enter your own, and then click **Next** to go to the Connect to the Database page.

Note: You will need to enter this username and password in the repository definition (see *Installing the Repository to the Server* on page 24) and data source (see *Creating a Data Source to Access Your Database* on page 26).

8. Deselect the **Connect to the new database** option, and then click **Finish** to create the database.

Installing the Repository to the Server

The repository administrator must set up the repository on a database server running one of the supported DBMSs.


Note: Before you can install the repository, you must create an empty database with an administrator user who has full rights on all the tables (see *Creating a Database to Contain the Repository* on page 23) and install PowerDesigner on the repository administrator's workstation (see *Chapter 2, Installing PowerDesigner* on page 11).

1. On the repository administrator's workstation, start PowerDesigner and select **Repository > Repository Definitions** to open the List of Repository Definitions.
2. Click the **Add a Row** tool to create a new definition, and click the **Properties** tool to open its property sheet.
3. Enter the following properties:

Property	Value
Repository name	Enter an appropriate name to identify the repository.
Default login name	ADMIN

Property	Value
Default password	Leave this field blank. You will be prompted to enter a password once the repository has been created.
Data source name	Click the Select a Data Source tool to the right of the field and select or create the data source that you want to use to connect to the repository database. To create an ODBC machine data source for a SQL Anywhere database, see <i>Creating a Data Source to Access Your Database</i> on page 26. For detailed information about creating, configuring, and using connection profiles for other DBMSs, see <i>Core Features Guide > The PowerDesigner Interface > Getting Started > Connecting to a Database</i> .
User name	Enter the administrator name you chose when creating the database.
Password	Enter the administrator password you chose when creating the database
Bytes per char	For non-Oracle unicode or multi-byte character set databases, specify the bytes per character used by the database: <ul style="list-style-type: none"> • 1-byte - [default] For SBCS (Single-Byte Character Set) • 2-byte - For DBCS (Double-Byte Character Set) • 3-byte - For Unicode or MBCS (Multi-Byte Character Set)

4. Click **Test** to test the connection and, in the event of an error, double-check your connection parameters. Then click **OK** to return to your repository definition, and click **OK** to complete its creation.
5. Select **Repository > Connect** to open the Connect dialog. Select the name of the repository definition you just created and click **OK** to connect.
A message box is displayed inviting you to install the repository. This will involve running a SQL script to create the necessary tables.
6. Click **Yes** to continue. The read-only Repository Installation Script window opens.



Note: You cannot edit the script in this dialog, but you can, if necessary, modify the statements (for example, to add physical options) by copying the script to an external SQL editor, making the appropriate edits, and then connecting to the database to execute the script outside of PowerDesigner. The Separator list in the dialog lets you select the separator appropriate to your interpreter.

7. Click **Execute** to run the script and create the repository tables. This may take several minutes.

Note: If the installation fails due to network problems, insufficient disk space, or permission problems, we recommend that you do not choose to ignore the errors, but rather abort the installation and start again.

8. When the repository has been installed, the Change Password dialog will open, prompting you to change the administrator password. Enter a password that complies with the default repository password policy as listed in the dialog, and then click **OK** to complete the creation of the repository.

In the repository Browser, the root of the repository tree displays the repository name and the connected user and is ready for use.

Creating a Data Source to Access Your Database

In order for PowerDesigner to connect to your database, you must create a data source from within PowerDesigner or using the ODBC Data Source Administrator.

The instructions given here are for creating an ODBC machine data source for SQL Anywhere. For information about creating other data sources for other DBMSs, see *Core*

Features Guide > The PowerDesigner Interface > Getting Started > Connecting to a Database.

Note: In order to create a data source on a Windows 7 machine, you may need to launch PowerDesigner or the ODBC Data Source Administrator by right-clicking its icon or menu item and selecting **Run as administrator**.

1. Click the **Select a Data Source** tool on the Repository Definition dialog, then select **ODBC machine data source** and click **Configure**. On the **ODBC Machine Data Sources** tab of the Configure Data Connections dialog, click the **Add Data Source** tool, then select **System Data Source** and click **Next**.

Alternately, to create a data source using the ODBC Data Source Administrator, select **Start > Settings > Control Panel > Administrative Tools > Data Sources (ODBC)**, select the **System DSN** tab, and then click **Add**.

Note: In a 64-bit environment, you must use the 32-bit version of the ODBC Administrator tool, because PowerDesigner cannot connect to 64-bit ODBC DSNs (see *Windows 64-Bit Support* on page 9).

2. Select **SQL Anywhere 12** and click **Next**, and then click **Finish** to create the data source.
3. On the **ODBC** tab of the ODBC Configuration for SQL Anywhere dialog, enter an appropriate name such as PD Repository in the **Data source name** field.
4. Click the **Login** tab and enter the following values:

Parameter	Value
Authentication	Select Database.
User ID	Enter the administrator name you chose when creating the database (see <i>Creating a Database to Contain the Repository</i> on page 23).
Password	Enter the administrator password you chose when creating the database.
Action	Select the appropriate action: <ul style="list-style-type: none"> • Start and connect to a database on this computer • Start and connect to a database on another computer
Database file	Browse to and select your database file.
Database name	Enter an appropriate name such as PD Repository.
Server name	Enter an appropriate name such as PD Repository.
Start line	Enter "C:\Program Files\SQL Anywhere 12\Bin32\dbsrv12.exe" (including the quotation marks).

Parameter	Value
Stop database after last disconnect	Deselect this option if you want the repository to continue to be available after you disconnect from it.

- Click **OK** to complete the configuration of the data source.

Troubleshooting the Repository Installed on ASE

This section lists known issues encountered when installing the repository on Sybase Adaptive Server Enterprise.

Commonly Required ASE Parameters

The following ASE parameters must frequently be configured higher than their default settings to optimize check in of models:

- number of open objects
- number of open indexes
- number of locks
- max memory
- procedure cache size

Must declare variable '@dr_t_a0'. SQLSTATE = ZZZZ

If you see the above error and are connecting to an ASE server via ODBC, open the ODBC Data Source Administrator, select your data source, and select the **Enable Dynamic Prepare** option on the **Connection** tab.

Truncated data on extraction

If you are seeing data truncated on extraction from the repository and are connecting to an ASE server via ODBC, open the ODBC Data Source Administrator, select your data source, and enter the value 10000000 in the **Text size** field on the **Advanced** tab.

If characters such as the ellipsis are being truncated, you should verify that the character set of your driver matches the setting for your database.

Connection Profile: "Error converting characters into server's character set"

If you receive such a conversion error when working with a connection profile, click the ellipsis button to the right of the **Connection parameters** field on the Connection Profile Definition dialog, add the CharSet parameter, and enter the appropriate charset value to match your repository database.

Troubleshooting the Repository Installed on DB2

This section lists known issues encountered when installing the repository on IBM DB2.

Exception During Search

If you are seeing exceptions when performing a search through the PowerDesigner Portal, you should consider doubling the size of the `applheapsz` parameter, which controls the application heap size.

Connection Profile: "Error converting characters into server's character set"

If you receive such a conversion error when working with a connection profile, click the ellipsis button to the right of the **Connection parameters** field on the Connection Profile Definition dialog, add the `CharSet` parameter, and enter the appropriate charset value to match your repository database.

Troubleshooting the Repository Installed on SQL Server

This section lists known issues encountered when installing the repository on Microsoft SQL Server v2005 and higher.

Optimizing Repository Reads with Snapshots

To ensure that all users reading data will get access to a snapshot and not be blocked by concurrent transactions, we recommend that you enable the following SQL Server options:

- `ALLOW_SNAPSHOT_ISOLATION`
- `READ_COMMITTED_SNAPSHOT`

Note: No users should be connected to the repository when you enable these options.

Connection Profile: "Error converting characters into server's character set"

If you receive such a conversion error when working with a connection profile, click the ellipsis button to the right of the **Connection parameters** field on the Connection Profile Definition dialog, add the `CharSet` parameter, and enter the appropriate charset value to match your repository database.

Installing the Repository Proxy

The PowerDesigner repository proxy is an optional program that runs as a service on or near the repository server and translates SQL requests from client workstations into a more efficient proprietary format. The proxy can considerably improve performance, particularly if clients will be connecting over a WAN or complicated LAN environment or when dealing regularly with larger (15MB+) models, due to its client request pooling and sophisticated caching.

CHAPTER 3: Installing the Repository

Using the proxy also simplifies the client connection to the repository, as users do not need to know details of the database hosting the repository.

1. Choose whether to install the repository proxy on the repository server, or on another windows machine on the same LAN.

You should install the proxy on the same server as the repository, if possible, to optimize communication between the components. If the repository server is not a Windows server or is unable to support the additional workload, then we recommend installing the proxy on another machine on the same LAN segment. We recommend as a minimum, a dual-core machine, with 2-4GB of RAM, but the exact system requirements depend on the number of concurrent users and the size of your repository.

2. Create a system data source on the chosen machine to define the connection between the proxy and the repository database (see *Creating a Data Source to Access Your Database* on page 26).
3. Insert the PowerDesigner software CD-ROM in the drive, and then click the **Install PowerDesigner Repository Proxy** button.
4. Click **Next** to go to the license agreement page. Select the location where you are installing the software, read the License Agreement, and then click the **I Agree** radio button to accept the terms of the agreement. If you click **I Do Not Agree**, you cannot proceed with the Setup program.

Note: You can print the License Agreement from the Setup\Licenses directory on the product CD.

5. Click **Next** to go to the directory selection page. Accept the default installation directory or choose another by clicking the **Browse** button.
6. Click **Next** to go to the current settings page to review your choices, and then click **Next** to start copying files.

When setup is complete, a page is displayed with two checkboxes selected by default, to let you start the proxy service and launch the configuration tool.

7. Click **Finish** to exit the wizard and open the Proxy Configuration dialog.

Note: You must have write access on HKEY_LOCAL_MACHINE to change proxy parameters. On a Windows 7 machine, you may need to launch the Proxy Configuration dialog by right-clicking its icon and selecting **Run as administrator**. You can open the configuration dialog at any time by navigating to the proxy installation directory and launching `pdproxyconf16.exe`.

8. Click **New** to create a new proxy connection instance, and enter the following parameters.

Parameter	Value
Instance name	Enter an appropriate name to identify the instance.

Parameter	Value
Data source	Select the system data source you created for the repository from the list. Note that the proxy cannot access user data sources.
User name	Enter the user name used to connect to the repository database.
Password	Enter the password used to connect to the repository database.
Bytes per char	For non-Oracle unicode or multi-byte character set databases, specify the bytes per character used by the database: <ul style="list-style-type: none"> • 1-byte - [default] For SBCS (Single-Byte Character Set) • 2-byte - For DBCS (Double-Byte Character Set) • 3-byte - For Unicode or MBCS (Multi-Byte Character Set)
Port	Enter the connection port of the server on which the proxy is installed and which allows the client to communicate with the server using TCP/IP protocol. The default port number is 32999.
Log file	Select the level of logging that you want to perform and enter or browse to the path to the log file in the Name field.
Cache	Enter or browse to the path to the cache, and specify its maximum size. The default is 300MB, which is generally sufficient for optimum proxy performance.

Note: A single proxy server can provide simultaneous connections to multiple PowerDesigner repositories of the same version. Click the **New** button to create an additional instance.

9. Click **OK** to complete your definition of proxy instances.

Users can now connect to the repository via the proxy by specifying the server name, port number and instance name in a proxy repository definition (see *Core Features Guide > The PowerDesigner Interface > Getting Started > Accessing the Repository*).

Installing the PowerDesigner Portal Server

The PowerDesigner Portal allows you to view the contents of your repository in your standard web browser. The PowerDesigner installation disc includes database access and web application layers that are required to browse your repository from the web, along with a standard Apache Tomcat web server. Before beginning the installation, you should already have created your repository database and have the DBMS user name and password to hand.

For maximum responsiveness, we recommend that you install the database access layer on the same machine as your repository database, while the web application layer can be installed on any appropriate machine. While each instance of the PowerDesigner Portal database access layer can only communicate with a single repository database, a single web application

instance can communicate with multiple database access layers and provide a single point of access for users browsing multiple repositories.

If the repository server is not a Windows server or is unable to support the additional workload, then we recommend installing the PowerDesigner Portal on another machine on the same LAN segment. We recommend as a minimum, a dual-core machine, with 2-4GB of RAM, but the exact system requirements depend on the number of concurrent users and the size of your repository.

Note: For information about using the PowerDesigner Portal, see *Core Features Guide > The PowerDesigner Interface > The PowerDesigner Portal*.


1. Insert the PowerDesigner software CD-ROM in the drive, and then click the **Install PowerDesigner Portal** button.

The PowerDesigner Portal installation program opens to the welcome page.

2. Click **Next** to go to the license page, and select the type of license that you want to use:
 - **Trial** - For evaluating PowerDesigner and the PowerDesigner Portal
 - **PowerDesigner Portal** - For using the PowerDesigner Portal without allowing users to edit object comments, descriptions, and annotations
 - **PowerDesigner Portal Composer** - For allowing users to edit object comments, descriptions, and annotations, which requires a separate license. If you select this option, you will be prompted to specify the licence server that manages this license (see *Installing a License Server* on page 4).
3. Click **Next** to go to the license agreement page, and select the location where you are installing the software. Read the License Agreement and click the **I Agree** radio button to accept the terms of the agreement. If you click **I Do Not Agree**, you cannot proceed with the Setup program and you will have to cancel the install.


Note: You can print the License Agreement from the Setup\Licenses directory on the product CD.

4. Click **Next** to go to the web server page. If you have already installed one or more PowerDesigner Portal servers, you can select the second option to install the web application layer only. You will then be prompted to specify connection information for a PowerDesigner Portal server to which it will connect. Setup suggests a location in which to install the PowerDesigner Portal, which you can change by clicking the **Browse** button.



5. Click **Next** to go to the application server page. By default, the installer will install a new Tomcat Server. If you want to use one of the other supported servers, select it and specify its location. Default sever ports may be provided that you must verify. At least one port is required in order to create a connection profile and connect to the repository database.

Note: If you choose the WebLogic application server, you must deploy the archive directory (by default, the `weblogic_openfolder` directory inside your PowerDesigner Portal installation directory) from your WebLogic Administrative Console once the setup has completed.



6. Click **Next** to go to the JDK page. By default, a new JDK is installed. If you want to use an existing JDK, deselect the check box and specify its location.
7. Click **Next** to go to:
 - [for a full PowerDesigner Portal server install] The database parameters page lets you enter the appropriate parameters for your database. If you select the **Use Windows Authentication** checkbox, you will need to select the **This account** option on the **Log On** tab of the web server service property sheet before starting the service.

Sybase PowerDesigner Portal 16.0

Sybase® PowerDesigner Portal 16.1

Specify the database parameters for your repository. If your repository is stored in a DBMS other than Sybase SQL Anywhere or ASE, you must specify an appropriate JDBC driver jar file.

Database type: Sybase SQL Anywhere

JDBC driver class: com.sybase.jdbc3.jdbc.SybDriver

JDBC driver jar: jconn3.jar

Host: localhost Port: 2638


Database name:

User: dba Password:

Use Windows Authentication

SYBASE An SAP Company

- [for an application layer only install] The connection information page of the PowerDesigner Portal server lets you enter the appropriate parameters for connecting to the existing repository web server instance. You must enter at least one port:



8. Click **Next** to go to the information page which summarizes your choices.
9. Click **Next** to accept the current settings and start copying files.

The install begins. A progress box is displayed and Setup copies files to the destination directory. When the setup is complete, one of the following pages appears depending on your selection on the web server page:

- [PowerDesigner Portal server] The completion page opens with two check boxes selected by default to let you:
 - Start the PowerDesigner Portal Server service
 - Open the PowerDesigner Portal Web page
- [web application layer] The completion page opens with a check box selected by default to let you open the service configuration page and enter its account name and password. Then you will have to start the service.

10. Click **Finish** to exit the wizard.

Accessing the PowerDesigner Portal Web Site

You can start and stop the PowerDesigner Portal server and the associated service by navigating to the server from your Start menu.

By default, these commands appear as sub-items of **Programs > Sybase > PowerDesigner Portal**, and selecting the appropriate sub-item:

- Start the PowerDesigner Portal Server
- Start the PowerDesigner Portal Server Service
- Stop the PowerDesigner Portal Server
- Stop the PowerDesigner Portal Server Service

When the server is running (whether as a service or not), navigate to the following address:

`http://server-name:port-number/cmz`

Where *server-name* is the name of the machine on which you have installed the PowerDesigner Portal server, and *port-number* is the port specified during installation. Note that *cmz* is the name of the PowerDesigner Portal program and is a required part of the address.

The following screen will appear:

The screenshot shows the Sybase PowerDesigner Portal login interface. At the top, there is a blue header with the SYBASE logo on the left and 'PowerDesigner Portal' in the center, accompanied by a database icon on the right. Below the header, the main content area has a light blue background. It starts with the text 'Sign in to Sybase PowerDesigner Portal. To sign in, select a connection profile, enter user name and password.' Below this is a form with a 'Connection profile:' label and a dropdown menu currently showing 'LOCAL'. There are two links: 'Show profile information' and 'Advanced options'. Further down are 'User name:' and 'Password:' labels with corresponding input fields. To the right of the password field is a 'Logon' button with a user icon and a 'Help' link.

For information about using the PowerDesigner Portal, see *Core Features Guide > The PowerDesigner Interface > The PowerDesigner Portal*.

PowerDesigner Portal Security

All passwords saved in the repository configuration files are encrypted and are decrypted at runtime. User passwords are encrypted when making connection to the repository.

The default keys used for the encryption and decryption process are saved in the following file:

```
install_dir/keystore/common.keystore
```

For security purposes, we recommend that you generate your own key and keystore file. The keystore information is saved in the following file:

```
install_dir/keystore/config/cmzcommon.xml
```

CHAPTER 3: Installing the Repository

This file contains the following XML structure:

```
<cmrcommon>
  <!-- Keystore Configuration -->
  <bean class="java.lang.Object" id="cmr.common.config.keystore">
    <!-- if value is empty, default to cmr home\keystore folder
-->
    <param name="keyStoreFilePath" value="" />
    <param name="keyStoreFileName" value="common.keystore" />
    <param name="keyStoreAlias" value="cmrenkey" />
    <param name="keyStorePassword" value="changeit" />
  </bean>
</cmrcommon>
```

You can edit the following nodes:

- `keyStoreFilePath` – Specifies the path to the keystore file. Default value: *install_dir/keystore/*.
- `keyStoreFileName` – Specifies the name of the keystore file.
- `keyStoreAlias` – [required] Specifies the name of the alias of the key in the keystore.
- `keyStorePassword` – [required] Specifies the password to read the keystore.

You can use the following command to generate a 512 byte key and keystore file:

```
JDK_HOME\bin\keytool -genkey -keyalg RSA -keysize 512 -alias
keyStoreAlias -keypass keyStorePassword -keystore keyStoreFilePath
\keyStoreFileName -storepass keyStorePassword
```

For example: to generate a new key using the default values specified in the `cmrcommon.xml` file:

```
JDK_HOME\bin\keytool -genkey -keyalg RSA -keysize 512 -alias
cmrenkey -keypass changeit -keystore install_dir\keystore
\common.keystore -storepass changeit
```

Note that all PowerDesigner Portal web application layer installations that need to connect to a PowerDesigner Portal Server must use the same keyStore file. We recommend that you update periodically the key in the keystore. If a new key is being used, make sure to change the passwords in *install_dir/keystore/config/repository.xml* file to a plain password. PowerDesigner Portal will automatically encrypt any plain passwords in this file.

For example: the database access password.

```
<bean
class="com.sybase.cmr.infra.server.persistence.db.connection.DBCPCo
nnectionProvider"
  id="cmr.connection.provider">
  <param name="databaseProfile" value="asa90.xml" />
  <param name="dbtype" value="Sybase ASA 10.x" />
  <param name="connectionURL"
    value="jdbc:sybase:Tds:localhost:2638" />
  <param name="jdbcDriverClass"
    value="com.sybase.jdbc3.jdbc.SybDriver" />
  <param name="dbhost" value="localhost" />
  <param name="dbport" value="2638" />
```

```

<param name="dbname" value="" />
<param name="user" value="dba" />
<param name="password" value="sql" />
<param name="initialPoolSize" value="1" />
<param name="minIdle" value="1" />
<param name="maxIdle" value="3" />
<param name="maxWait" value="2" />
<param name="maxActive" value="10" />
<param name="isolationLevel" value="1" />
</bean>

```

The mail server password:

```

<bean class="java.lang.Object" id="cmr.server.config.smtp">
  <param name="mail_notification_resume" value="true" />
  <param name="mail_notification_include_before_resume"
value="false"/>
  <param name="smtp_host" value="" />
  <param name="smtp_port" value="" />
  <param name="default_sender_email" value="" />
  <param name="smtp_ssl" value="false" />
  <param name="smtp_auth" value="false" />
  <param name="smtp_auth_account" value="" />
  <param name="smtp_auth_password" value="" />
  <param name="smtp_password_authentication" value="false" />
  <param name="mail_template_name" value="mail.template.xml" />
</bean>

```

Installing the PowerDesigner Portal Server on UNIX

We do not provide support for installing any component of PowerDesigner on UNIX. However, it is possible to manually deploy the PowerDesigner Portal to a UNIX environment using this procedure.

Note: This procedure requires that you install and configure the PowerDesigner Portal on a Windows server in order to copy certain of the installation directories to your UNIX installation.

1. On your UNIX server, install JDK 6.0 or higher, and set the JAVA_HOME environment variable to its path. For example:

```
export JAVA_HOME=/usr/lib/jvm/java-6-sun
```
2. Install Tomcat 5.5 or 6.0 and set the CATALINA_HOME environment variable to its path. For example:

```
export CATALINA_HOME=.../apache-tomcat-6.0.28
```
3. Create a new folder called CMR, and set the CMR_HOME environment variable to its path. For example:

```
export CMR_HOME=.../CMR
```
4. Copy the contents of the CMR_HOME directory on your Windows environment to the CMR_HOME directory on the UNIX server.

CHAPTER 3: Installing the Repository

5. Extract the appropriate license library for your flavor of UNIX from `CMR_HOME/license/lib/sylapi 2.2.0.7.zip` to `CMR_HOME/license/lib`.
6. Copy the `cmr.war` file from the `CATALINA_HOME/webapps` directory on your Windows environment to the `CATALINA_HOME/webapps` directory on the UNIX server.
7. Unzip `cmr.war` and edit the file `cmr.war/WEB-INF/cmhome.xml` to remove the content of the `Path` element, so that it reads `<entry key="Path"></entry>`. Rezip `cmhome.xml` into a new `cmr.war` and deploy the new `cmr.war`.
8. Ensure you have installed the necessary JDBC drivers to connect to your PowerDesigner Repository, and that they can be found via the proper path statement.
9. Run `CATALINA_HOME/bin/startup.sh`.

Multiple PowerDesigner Portal Instances on One Server

We do not provide support for running multiple instances of the PowerDesigner Portal on a single physical server. However, it is possible to manually configure your installation to do so using this procedure.

1. Install the initial PowerDesigner Portal normally.
In this example, we will install the Portal to `C:\Portal`:
2. Create a second installation directory for the second instance of the Portal, and add a sub-directory to hold the second instance of Tomcat.
In this example, we will create a second installation directory at `C:\Portal2`
3. Install the second Tomcat or other server to `C:\Portal2\Tomcat` and specify a different listening port.
In this example, we will use port number 3030 for the first Tomcat and 9090 for the second instance
4. Copy `C:\Portal\Tomcat\webapps\cmr.war` to `C:\Portal2\Tomcat\webapps\cmr.war`. For the remainder of this procedure, the file must be unzipped, as it will be if Tomcat is running.
5. Copy the folders `config`, `log`, `keystore`, and `license` from `C:\Portal` to `C:\Portal2`.
6. Edit `C:\Portal2\Tomcat\webapps\cmr\WEB-INF\cmhome.xml` to specify your new folder:

```
<entry key="Path">C:\Portal2</entry>
```
7. Clear `C:\Portal2\Tomcat\work` and restart Tomcat.

The URL for accessing the first PowerDesigner Portal is `http://myserver:3030/cmr/` and the URL for the second is `http://myserver:9090/cmr/`.

The new instance will initially point to the original database. You can change the database:

- By clicking the **Advanced options** link on the login page.
- By editing `C:\Portal2\config\repository.xml`

Changing the Repository DBMS

If you decide to change the DBMS on which the repository database is stored, then you must copy an appropriate JDBC driver to the `PowerDesigner Portal 16\Tomcat\webapps\cmr\WEB-INF\lib` directory to allow the PowerDesigner Portal to connect to the new database.

We recommend that you keep your original database running initially and that you change the parameters on the PowerDesigner Portal Server Settings page, and use the **Test Connection** button to confirm that you can connect to the new database.

Upgrading the Repository

When an administrator upgrades their PowerDesigner client and then connects to an existing repository for the first time, they will be prompted to upgrade the repository. Until an administrator upgrades the repository, other users who have upgraded their PowerDesigner client will not be able to connect to the repository.

Warning! Always back up your repository database before upgrading it. Upgrading the repository typically creates many log entries, and you should consider increasing the log size to accommodate them.

1. If you have installed the PowerDesigner Portal, you must stop the PowerDesigner Portal Service before upgrading the repository.
2. Open PowerDesigner and select **Repository > Connect** to open the Connect dialog. Only the PowerDesigner modules that are installed on your machine will be upgraded in the repository database. For example, if you do not have the Object Oriented Model installed on your machine, that part of the repository database will not be upgraded. For this reason, you should try to perform the upgrade from a machine that has all of the modules used by your organization installed.
3. Select a direct repository definition from the list, enter your password, and click **OK**.

Note: Upgrading the repository via the proxy is not supported.

4. You are prompted to update the repository. Click **Yes** to continue and open the Repository Update Script dialog.

Depending on the size and complexity of your repository, this dialog may take several minutes to appear.

Note: If you created your repository database with Microsoft SQL Server or Sybase ASE before PowerDesigner version 15.0, we recommend that you select **Rebuild clustered indexes** in this dialog to improve performance, particularly for document check out. If you

do not select this option at upgrade time, you can select **Repository > Administration > Rebuild Clustered Indexes** at any time to perform the rebuild.

5. Click **Execute** to begin the repository upgrade.

The upgrade may take some time to complete. In the event of an upgrade failure due to network or permission problems, or insufficient disk space, you should restore the repository database from your backup version and retry an upgrade when problems are solved. If the upgrade fails because of the data in your database, then you should contact technical support for assistance.

6. [when upgrading from a repository before v16.1] If your repository contains branches, you are prompted to update your branches to the new implementation (see *Post-Upgrade Cleanup for a Repository Containing Branches* on page 42). Click **OK** to continue.

Note: Depending on the complexity of your branch structure and the size of your repository, upgrading your branches may take a considerable time. If you click **Cancel** at this point you will leave the repository in a stable state, and can relaunch the upgrade at a later point by reconnecting to the repository.

7. [when upgrading from a repository before v16.1] If your current password does not comply with the default repository password policy, you will be prompted to change your password. Enter your new password (which must comply with all the rules listed in the dialog) and then click **OK**.

Note: Administrators can control the restrictiveness of the password policy (see *Core Features Guide > Administering PowerDesigner > Controlling Repository Access > Defining a Password Policy*).

8. The Library Synchronization dialog opens to prompt you to synchronize the contents of your local library. Make any appropriate selections and click **OK** to perform the synchronization and complete the repository upgrade.

For information about administering the library, see *Core Features Guide > Administering PowerDesigner > Deploying an Enterprise Glossary and Library*.

Post-Upgrade Cleanup for a Repository Containing Branches

The new implementation of repository branches provides many improvements over branches in v16.0 and earlier, but if your existing repository contained branches, you may want to perform some post-upgrade cleanup of your updated branch structure or create a new repository and migrate all your active documents to it.

For v16.1, branches in the repository have been completely re-architected to allow:

- The simultaneous display of all branches in the repository browser.
- Branching on a folder-by-folder basis.
- Simplified version numbering.
- Greater flexibility and control over branch contents.
- Simplified integration of changes from one branch to another.

During the repository upgrade, PowerDesigner will transform any existing branches in your repository to the new format, and your new repository will display all of your old branches as siblings directly under the root. As a result, you may experience the following issues:

- Too many branches at root making the repository difficult to view and navigate. To simplify your repository, you should consider:
 - Hiding branches when they are not needed for certain users.
 - Deleting old branches that are no longer needed for any users.

Note: For information about working with the new repository branches, see *Core Features Guide > The PowerDesigner Interface > The Repository > Branching Version Trees*.

- The presence of branches at the root prevents you from being able to branch sub-folders (because you cannot create a branch under another branch).

To simplify a repository and enable the creation of branches on a folder-by-folder basis, you should create a new repository and transfer all your appropriate models and other documents to it.

1. Review your existing repository and identify the models and other documents that are still current and that you want to transfer to your new repository.
2. Create a new repository and create all the necessary users and groups in preparation for allowing your users to connect to it.
3. Set up an appropriate folder structure to allow you to organize your documents by project, and in preparation for future branching.
4. Connect to your old repository and check out all the documents you want to transfer.

Note: To ensure that no changes are lost, you may want to perform the remaining steps outside of normal working hours or instruct your users to terminate their connections with the old repository and await permission to begin connecting to the new repository.

5. Connect to your new repository and check the documents to transfer into it.

Note: When you check documents into the new repository, their revision histories will not be transferred with them. For this reason, you may want to retain, at least for a time, your old repository to give you continuing access to this information.

6. Continue transferring documents until everything that you need for ongoing development is in the new repository and organized in an appropriate folder structure.
7. Communicate the new repository connection information to your users and instruct them from now on to only check documents in and out of the new repository.

Deleting the Repository

You can delete the repository by using the **Drop Repository Tables** command, which removes all repository tables and their content from the database and cuts the connection with

CHAPTER 3: Installing the Repository

the database. You cannot drop the repository tables through a proxy connection. You must perform a direct ODBC connection instead.

Warning! Dropping the repository database cannot be undone. If you have not backed up your models and other contents, they will be lost.

1. Select **Repository > Administration > Drop Repository Tables**. You will be prompted to confirm that you want to continue. Click **Yes** to open the Repository Table Drop Script window.

This window is read-only. You can only review the script, and not edit it. If you want to modify the script you should copy it to a script interpreter, after having selected the appropriate separator for your interpreter from the list.

2. Click **Execute** to begin the deletion.

Index

64-bit support 8, 9

A

Adaptive Server Enterprise
troubleshooting 28
administrative install 15
install client machines 16
authenticate
existing database 22
new database 22
authenticate.sql 22

B

backup repository database 41
branch 8
upgrade to 16.1 42

C

client
install 16
client/server environment 21
computer name 3
create database 23

D

data
encryption 9
data source 26
database
create 21, 23
data source 26
drop repository 43
repository 21
size 24
upgrade 41
DB2
troubleshooting 29
dependencies 20
diagnostic program 4
disconnect repository 43

disk space 16

E

Eclipse plug-in 11
encryption 9

F

floating served license
impossible to return 4
limitation 4
font
general options 20
report 20
symbol 20

G

general options font 20

H

host ID 3

I

install
administrative mode 15
authenticated server 22
copy files on server 16
Eclipse plug-in 11
font problem 20
license server 4
maintenance 19
network location 16
non-administrator user 11
PowerDesigner 11
PowerDesigner Portal 31
repository proxy 29
silent 17
SQL Anywhere 22
upgrade administrative version 17
Visual Studio plug-in 11

Index

IPv4 8

IPv6 8

L

license file 3

license server

install 4

license file 4

manage licenses on server 7

reread 4

start 4

LMTOOLS 4, 7

LMUTIL 4, 7

M

maintenance

modify 19

remove 19

repair 19

modify install 19

N

network location 16

O

ODBC 26

P

password

encryption 9

PowerDesigner

administrative install 15

current setting 11

install 11

README 11

upgrading 8

PowerDesigner Portal 21

accessing 36

change DBMS 41

install 31

keystore 37

multiple instances 40

security 37

UNIX install 39

proxy

install 29

repository 21

proxy connection 41

R

readme.html 11

rebuilding clustered index 41

remove install 19

repair install 19

repository

Adaptive Server Enterprise 28

backup database 41

branch 8, 42

change DBMS 41

create database 21

create ODBC system data source 26

database size 24

database upgrade 41

DB2 29

drop script 43

drop tables 43

install 22, 29

rebuilding clustered index 41

SQL Server 29

upgrade 41, 42

upgrade failure 41

repository proxy 21

reread license file 7

reread license server 4

resource files 8

response file 17

return

floating served license 4

standalone served license 4

S

server

check disk space 16

copy files 16

database 21

install 22

install license server 4

manage licenses 7

SQL Anywhere 22

- settings
 - PowerDesigner 11
 - setup.iss 17
 - setup.log 17
 - silent install 17
 - response file 17
 - SPDC 3
 - SQL Anywhere
 - authenticated server 22
 - install 22
 - network authenticated server 22
 - repository 22
 - SQL Server
 - troubleshooting 29
 - standalone local license 3
 - standalone served license
 - impossible to return 4
 - limitation 4
 - start license server 4
 - Sybase Product Download Center 3
 - SySAM
 - 64-bit support 8
 - IPv4 8
 - IPv6 8
 - UNIX 8
 - Windows 64-bit 8
 - system data source 26
- ## U
- UNIX 8
 - PowerDesigner Portal 39
 - upgrade 41
 - administrative install 17
- ## V
- Visio add-in 8
 - Visual Studio plug-in 11
- ## W
- web browser
 - install 31
 - keystore 37
 - security 37
 - Windows 64-bit 8, 9
 - Word 8

