



CYBER Save Editor for PS4 Instructions

Please read this manual before using the product.

Preface

Thank you very much for purchasing *CYBER Save Editor for PS4*. Do not lose the packaging and setup guide if you purchased a physical version, or the confirmation email (with the serial key) that we sent to your email address if you purchased a download version. These documents contain information that may be necessary to receive customer support.

About this product

CYBER Save Editor for PS4 is a software application that lets you use “patch codes” or “cheats” to modify your PS4 save data. Effects include unlocking additional gears and secret levels, and maxing in-game stats like money, life, and ammunition without going through the grind.

- This product is a CYBER Gadget original product, not a licensed product of Sony Interactive Entertainment Inc.
- All authors and agents involved in the manufacture and distribution of this product will not be held responsible for any damages, whether direct or indirect, inevitable or accidental, arising from the use or misuse of this product. The same holds true even if the authors were notified of possible damage beforehand.
- Product specifications are subject to change without prior notice for product improvement.
- Copying, duplicating, or modifying the product, in whole or in part regardless of its form, without permission, is strictly prohibited.
- There will be a notification at least a month early on our official website in the inevitable possibility that the product may stop functioning due to events such as but not limited to PS4 system software upgrade or product specification development.


- This product may become unusable due to PS4 system software update. When PS4 releases a new update, make sure to check our newsfeed or website for announcements first before you download any updates.

Usage Notes

- We are not accountable for any damage in or loss of save data or patch code (which the user added) that may occur during the use of this product.
- In the event that the game stopped working while playing, press and hold the power button for seven seconds to force shut down the system, then turn the power back on again.
- Selling, copying, altering, lending, or assigning this product without permission from CYBER Gadget is strictly prohibited.
- Selling, lending, or assigning any saved data that reflects the use of this product, as well as recording the said saved data on any media, are strictly prohibited.
- This product cannot be used with online or network games according to its specifications. However, we cannot guarantee that this product will not be usable in a way different from its intended use, or with online games due to defects and game specification changes. Under these terms, you agree not to use this product outside its intended use.
- Reverse engineering or disassembling this product and other such activities without permission are strictly prohibited.
- You shall not engage in any other activities not mentioned above that may be alleged to infringe the copyright of game authors.

Contents

One of the following documents is included when you purchase Save Editor (depending if it's a physical or a download version). Read it carefully before using the product. In case of defect, contact the store where you directly made the purchase or email CYBER Gadget Customer Support.



Operating Environment

Make sure the operating environment is set up correctly.


- PC with Internet connection (Requires Windows 7 or higher)
 - * Not applicable with Mac
 - * Tethering is not recommended due to large data transfer size
- PlayStation 4 and PSN ID
- USB flash drive: 8GB or higher
 - * You need to copy desired save data onto a USB flash drive and apply desired patch codes from a computer
- Hard drive free space: 10GB or higher

Let's Get Started!


You need to register your serial key and create a user account.

Register Serial Key

- 1
- After installing the software, click on the Save Editor icon on your desktop. A dialogue box will appear.



- 2
- Enter the product serial key in the dialogue box and click OK.



Serial Key




Serial Key

Continue to create an account.

User License

User license configuration is as shown below.




Create a User Account

You need a PSN ID and PS4 save data to create an account.

* PS4 game save data

Each user's save data will be managed separately even if they're on the same game.

Example



For example, User A cannot use Save2 and User B cannot use Save1. Likewise, User A can only edit the save data with his registered account on Save Editor, and User B can only edit the save data with her registered account.





If you accidentally created an account with a different PSN ID, you can delete this account. However, there is a limit so you have to be careful. See [Deleting Accounts under Settings](#).


First Step (PlayStation 4)

- ① Insert your USB flash drive to your PlayStation 4 system and turn the power on. Log on with the PSN account that you want to use on Save Editor.

* You won't be able to have the option [Copy to USB Storage Device] later if you don't log on.


- ② Go to [Settings] → [Application Saved Data Management] → [Saved Data in System Storage] → [Copy to USB Storage Device]





- ③ You will see a list of all your save data. Put a check on the ones that you want to copy, then click [Copy].


* You can see the file size of every save data on the list. Choose a small file size if possible.




The next step will be on your computer.

Second Step (Computer)

- ① After entering the serial key on Save Editor, there will be a prompt to create an account. Insert the USB flash drive that contains your PS4 save data, then click [Next].



- ② Enter a user name, then click [Register].




You have successfully created an account.

Let's Use Save Editor!



Get a leg up on your favorite games with *CYBER Save Editor* now! Easily apply patch codes to your games for unlimited money, ungraded weapons, unlocked characters, and much more.



How to Use

- ① Insert USB flash drive onto PS4 system and log on to your desired PSN account.




- ② Go to [Settings] → [Application Saved Data Management] → [Saved Data in System Storage] → [Copy to USB Storage Device].






③ You will see a list of all your save data. Put a check on the ones that you want to edit, then click [Copy].



- ④ Move the USB flash drive to your computer.




- ⑤ Run Save Editor and choose your desired patch codes, then click [Apply].



* New Patch Codes can be added.


[→Apply Patch Code](#)

[→Add Patch Code](#)





- ⑥ Move the USB back to your PS4 system, then go to [Settings] → [Application Saved Data Management] → [Saved Data on USB Storage Device] → [Copy to System Storage]. You will see a list of save data from your USB.






⑦ Select the save data that you edited on Save Editor, then click [Copy].



- ⑧ You will see the prompt, “Do you want to over write this saved data?” Click [Yes].



- ⑨ The patch codes are now enabled. See the effects of Save Editor and enjoy!


* Some patch codes may not work properly on certain games.



Main Window

Game List Tab

The image below is the default screen when you run Save Editor. You can see the setting and the list of supported games.



① Game

All game titles supported by Save Editor will be displayed if your USB flash drive is NOT plugged into the computer. On the other hand, if the USB flash drive with your save data is plugged in, ONLY the game titles that correspond to your save data will be displayed. You have the option to display all game titles by checking the [Show All] box at the bottom.

- Game titles in black letters: games with one save data
- Games titles with ▶ before them: games with more than one save data
- Game titles in gray letters: no save data on USB

* Go to About User License for more details.

② Cheats

Displays the number of registered patch codes.

③ Game ID

Displays the game model number

④ Setting





Opens the Setting tab

⑤ Help

Directs you to Save Editor instruction manual

⑥ Server Status

Displays Save Editor's server traffic status. Save Editor may have limited function depending on the server's status.


Normal		Blue : All functions are working
Congested		Yellow : Advanced mode is not working
Suspended		Red : Server is down temporarily due to maintenance
		Gray : Internet is not connected

⑦ Select USB Drive

Choose the USB device that has your PS4 save data

Setting Tab

This tab contains Save Editor's backup folder, account cancellation option, and other options.



①Backup Saves

Keep this option checked to create automatic backups of your save data every time:

- ① You apply patch codes
- ② You edit the save data and apply patch codes (Advanced Mode)

All backup files are stored with the name format below. Do NOT change the file name as you won't be able to restore your save data should you want to.

SavedDataNumber_SavedDataType_Date

②View News

View the news shown during startup.

③Delete Account


Deletes selected account.

* There is a 30-day wait period every time you use the "Delete Account" option. On the other hand, there is no wait time to use the "Create Account" option.

Sub Window

Quick Mode

Simply select your desired patch codes.



①Name

You can see the list of available patch codes for the selected game.

- Default Patch Code list: cannot be edited or deleted. To add new Patch Codes, right click anywhere on the screen and select [Add Cheat].




②Comment

Comment is displayed.

Add Cheat Window

Right click anywhere on the Quick Mode screen and select [Add Cheat]. This will open the Add Cheat Window.



①Name

Enter a name for the Patch Code here.

*What you type in the Name and Comment sections will not affect the code.

②Comment

Enter a comment here about the Patch Code.

③Patch Code


Enter the Patch Code here.



Incorrect codes may damage your save data. Be sure to read How to Add Cheat very carefully before you add new cheats.

Advanced Mode Window

You can freely edit your save data with the Advanced Mode. However, be warned that incorrect codes may damage your save data and that **CYBER Gadget Customer Support** cannot help with inquiries relating to the use of the Advanced Mode.



① Address

Save data address

② Data (Hex)

Hexadecimal data contents

③ Data (ASCII)

ASCII data contents

④ SaveData Cache / Cheats / Codes


Save data Cache, Patch code list, and Patch code data are displayed.

Patch Code


You can apply the available patch codes by following the steps below.

Apply Patch Code


① Similar to the steps on [How to Use Save Editor], insert the USB flash drive that has your save data, then double click on the game title that you want to apply patch codes on.






② Check all the Patch Codes that you want to use and click [Apply].





③ There will be a prompt that asks if you want to overwrite the save data. Click [Yes].




- ④ After you've overwritten your save data, move your USB to your PS4 system, then go to [Settings] → [Application Saved Data Management] → [Saved Data in USB Storage Device] → [Copy to System Storage]. You will see a list of save data from your USB.



- ⑤ Select the save data that you edited on Save Editor, then click [Copy].



- ⑥ There will be a prompt, "Do you want to over write this saved data?" Click [Yes].



- ⑦ The patch codes are now enabled. See the effects of Save Editor and enjoy!


* Use the [Restore Save Data](#) option if you want to restore the save data to before it was overwritten.




How to Add Cheat

Follow the steps below to add new cheats. If you want to use cheats, go to [Apply Patch Code](#) for instructions.


① Right click anywhere on the Quick Mode screen and select [Add Cheat]. This will open the Add Cheat Window.



② Enter a name for the Patch Code, a comment, and the actual code.



③ Click [OK] when you're done. You will see this new Patch Code in blue letters on the Quick Mode game list.



How to Edit Cheat

Hover your mouse over the Patch Code that you want to edit and select [Edit Cheat]. From here, you can edit the Patch Code just like when adding Patch Code.

*Default Patch Codes cannot be edited.

How to Delete Cheat

Hover your mouse over the Patch Code that you want to delete and select [Delete Cheat]. You will be prompted with a confirmation message "Are you sure you want to delete this Patch Code?" Click [Yes].

*Default Patch Codes cannot be deleted.

*Patch Codes cannot be restored once deleted.

Restore Save Data

You can restore your save data (i.e. when damaged) to previous state if you keep the "Backup Saves" option ON in the Setting.


* "Backup Saves" is initially set to ON.

How to Restore from Backup




- ① On the Game List tab, right click on the game that you want to restore then select [Restore from backup].

- ② The game will be automatically restored if you only have one backup location for it. Choose one if you have more than one backup location.



- ③ You will see on your screen, "Save data restored."




- ④ Move your USB to your PS4 system, then go to [Settings] → [Application Saved Data Management] → [Saved Data on USB Storage Device] → [Copy to System Storage]. You will see a list of save data on your USB.



- ⑤ Select the save data that you want to restore then click [Copy].



- ⑥ You will see the prompt, "Do you want to over write this saved data?" Click [Yes].



F.A.Q.

Q. Can I add game titles?

A. Unfortunately, you cannot add game titles on the list. However, supported games will be added continuously. Check the Newsfeed for updates when you start Save Editor.

Q. How come the patch codes don't work even after I apply them?

A. One of the following may be the issue:

① The game version is different.

If the game software is updated and the save data file gets modified, there is a possibility that the patch codes may not work.

* We continuously update patch codes as new versions of games come out, but if and when the current patch codes don't match with the latest game version leading to an error in your save data, use the [Restore from backup] function to return it to its state before your applied the patch code.

② The USB is write protected

Any sort of modification or deletion of a file is blocked.

③ The patch code you entered is incorrect.

Q. Why is Save Editor not loading?

A. The server is under maintenance or the installation was not correct. Also, the Internet may not be connected.

Q. Can I use another device besides a USB?

A. No. Use only a USB flash drive.

Q. Can I use a save data from my PSN sub account?

A. You can use any save data from any account.

Q. How do I update Save Editor?

A. Save Editor is automatically updated during startup when new versions are available.

Q. Can I delete my current account and create a new one?

A. Yes, you can delete your current account and create a new one right away. However, you have to wait for 30 days to be able to delete the new account.

Q. Why do I need my PSN logon information?

A. This is per PS4 product specification. You need your PSN logon information to access any PS4 save data that you save on a USB flash drive.

Handling of Personal Information

Based on the provisions of Personal Information Protection Law, CYBER Gadget Corporation will handle and protect customers' personal information with utmost care. Please refer to our webpage or contact our customer support for details.

Customer Support

If you have any questions or concerns about this product, please see [Let's Use Save Editor!](#) and [F.A.Q.](#) first. If you need further assistance, please go to the Customer Support page on our website.

CYBER Save Editor for PS4 Support webpage :
<http://cyberSave Editor.com>

- Specifications of this product may be changed without prior notice for improvement.
- The images used in this manual or in the packaging may differ from actual software content.
- Duplication or reproduction of this product is strongly prohibited.

First Edition : August 31, 2018