BECKHOFF New Automation Technology

Manual | EN

TF3500

TwinCAT 3 Analytics Logger

File Edit View Project Build Build 40244 (koaded) Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Solution Explorer Image: Solution TwinCAT Project Image: Solution TwinCAT Project Image: Solution Explorer Image: Solution Explorer Solution TwinCAT Project Image: Solution TwinCAT Project Image: Solution Explorer Image: Solution Explorer Image: Solution TwinCAT Project Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution TwinCAT Project Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution TwinCAT Project Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image: Solution Explorer Image:		1 X Sand (Sold) p: InoCAT Right The InoCAT Right Configuration	
Solution Explorer Team Explorer	Location: Solution: Solution name: TwinCAT Project Carter and Carter and		

Table of contents

1	Fore	word	. 5
	1.1	Notes on the documentation	. 5
	1.2	Safety instructions	. 6
2	Over	view	. 7
3 Installation			
	3.1	System requirements	. 8
	3.2	Licensing	. 8
4	Anal	ytics Workflow - First Steps	11
	4.1	Recording data from the machine	11
	4.2	Communication	14
	4.3	Historicize data	15
	4.4	Analyse data	20
	4.5	24h Analytics application	24
5	Tech	nical introduction	34
5	Tech 5.1	nical introduction Basic Concepts	-
5			34
5	5.1	Basic Concepts	34 35
-	5.1 5.2 5.3	Basic Concepts MQTT	34 35 39
-	5.1 5.2 5.3	Basic Concepts MQTT Data Compression	34 35 39 41
-	5.1 5.2 5.3 Conf	Basic Concepts MQTT Data Compression	34 35 39 41 41
-	5.1 5.2 5.3 Conf	Basic Concepts MQTT Data Compression iguration Basic settings	34 35 39 41 41 43
-	5.1 5.2 5.3 Conf 6.1	Basic Concepts MQTT Data Compression iguration Basic settings 6.1.1 TLS	34 35 39 41 43 46
-	5.1 5.2 5.3 Conf 6.1	Basic Concepts MQTT Data Compression iguration Basic settings 6.1.1 TLS Data Streams	34 35 39 41 41 43 46 49
-	 5.1 5.2 5.3 Conf 6.1 6.2 6.3 	Basic Concepts. MQTT. Data Compression iguration Basic settings 6.1.1 TLS Data Streams 6.2.1 Data Handling	34 35 39 41 43 46 49 51
6	 5.1 5.2 5.3 Conf 6.1 6.2 6.3 Samp 	Basic Concepts	34 35 39 41 41 43 46 49 51 53

1 Foreword

1.1 Notes on the documentation

This description is only intended for the use of trained specialists in control and automation engineering who are familiar with applicable national standards.

It is essential that the documentation and the following notes and explanations are followed when installing and commissioning the components.

It is the duty of the technical personnel to use the documentation published at the respective time of each installation and commissioning.

The responsible staff must ensure that the application or use of the products described satisfy all the requirements for safety, including all the relevant laws, regulations, guidelines and standards.

Disclaimer

The documentation has been prepared with care. The products described are, however, constantly under development.

We reserve the right to revise and change the documentation at any time and without prior announcement. No claims for the modification of products that have already been supplied may be made on the basis of the data, diagrams and descriptions in this documentation.

Trademarks

Beckhoff[®], TwinCAT[®], EtherCAT[®], EtherCAT G[®], EtherCAT G10[®], EtherCAT P[®], Safety over EtherCAT[®], TwinSAFE[®], XFC[®], XTS[®] and XPlanar[®] are registered trademarks of and licensed by Beckhoff Automation GmbH.

Other designations used in this publication may be trademarks whose use by third parties for their own purposes could violate the rights of the owners.

Patent Pending

The EtherCAT Technology is covered, including but not limited to the following patent applications and patents:

EP1590927, EP1789857, EP1456722, EP2137893, DE102015105702 with corresponding applications or registrations in various other countries.

Ether CAT.

EtherCAT[®] is a registered trademark and patented technology, licensed by Beckhoff Automation GmbH, Germany

Copyright

© Beckhoff Automation GmbH & Co. KG, Germany.

The reproduction, distribution and utilization of this document as well as the communication of its contents to others without express authorization are prohibited.

Offenders will be held liable for the payment of damages. All rights reserved in the event of the grant of a patent, utility model or design.

1.2 Safety instructions

Safety regulations

Please note the following safety instructions and explanations! Product-specific safety instructions can be found on following pages or in the areas mounting, wiring, commissioning etc.

Exclusion of liability

All the components are supplied in particular hardware and software configurations appropriate for the application. Modifications to hardware or software configurations other than those described in the documentation are not permitted, and nullify the liability of Beckhoff Automation GmbH & Co. KG.

Personnel qualification

This description is only intended for trained specialists in control, automation and drive engineering who are familiar with the applicable national standards.

Description of symbols

In this documentation the following symbols are used with an accompanying safety instruction or note. The safety instructions must be read carefully and followed without fail!

▲ DANGER

Serious risk of injury!

Failure to follow the safety instructions associated with this symbol directly endangers the life and health of persons.

A WARNING

Risk of injury!

Failure to follow the safety instructions associated with this symbol endangers the life and health of persons.

Personal injuries!

Failure to follow the safety instructions associated with this symbol can lead to injuries to persons.

NOTE

Damage to the environment or devices

Failure to follow the instructions associated with this symbol can lead to damage to the environment or equipment.



Tip or pointer

This symbol indicates information that contributes to better understanding.

2 Overview

The TwinCAT Analytics Logger records process and application data of the machine controller in synchronization with task cycles. The logger is characterized by its high performance as it operates directly in the real-time context of the TwinCAT controller.

The TwinCAT Analytics Logger may either act as an MQTT client and transmit the data to a MQTT message broker on a regular basis (called MQTT-mode) or store the data locally in a file on the hard disk of the machine controller (called file-mode). The configuration required is performed in Microsoft Visual Studio®. All variables of the process image and the PLC application can be added easily to the configuration via check boxes without the need for programming.

When used as an MQTT Client the Logger is able to bypass short disconnects to the Message Broker using a ring buffer functionality to prevent loss of data temporarily. Used in file-mode, a ring buffer can also be configured, which may be useful in case of limited storage capacity or if there is no need for data to be recorded (henceforth referred to as logged) permanently, instead focusing on a fixed time interval.

The logged data may be used in various ways but its main intention is data analysis with TwinCAT Analytics as wells as data visualization with TwinCAT Scope.

Components

- Configuration surface in TwinCAT project tree
- Description files TcAnalytics.tmc and TclotBase.tmc
- Drivers TcAnayltics.sys and TclotDrivers.sys

List of key features

Functionality	TC3 Analytics Logger as MQTT Client	TC3 Analytics Logger for local storage
Programable record control	Yes	Yes
Configuration Interface	Yes	Yes
RT Context	Yes	Yes
MQTT	Yes	No
Analytics Binary Format	Yes	Yes
JSON Format	No	No
File Storage	No	Yes
Ring Buffer	Yes	Yes
Authentication	Yes	No
Encryption	Yes	Yes
Compression	Yes	Yes

3 Installation

The TwinCAT Analytics Logger is installed with TwinCAT XAE and XAR. Therefore, the Logger should always be available but in order to use it, one "TC3 Analytics Logger" license per target device is needed which may either be a permanent or a 7-day trial license.

For general information about licensing, please refer to the licensing paragraph below.

3.1 System requirements

Technical Data	TF3500 TC3 Analytics Logger
	Windows 7, Windows 8, Windows 10, WinCE PC (x86, x64 und ARM)
Min. TwinCAT Version	3.1.4022.31
Min. TwinCAT Level	TC1100 TC3 I/O

3.2 Licensing

The TwinCAT 3 function can be activated as a full version or as a 7-day test version. Both license types can be activated via the TwinCAT 3 development environment (XAE).


Licensing the full version of a TwinCAT 3 Function

A description of the procedure to license a full version can be found in the Beckhoff Information System in the documentation "<u>TwinCAT 3 Licensing</u>".

Licensing the 7-day test version of a TwinCAT 3 Function

Note: A 7-day test version cannot be enabled for a TwinCAT 3 license dongle.

- 1. Start the TwinCAT 3 development environment (XAE).
- 2. Open an existing TwinCAT 3 project or create a new project.
- 3. If you want to activate the license for a remote device, set the desired target system. To do this, select the target system from the **Choose Target System** drop-down list in the toolbar.
 - ⇒ The licensing settings always refer to the selected target system. When the project is activated on the target system, the corresponding TwinCAT 3 licenses are automatically copied to this system.
- 4. In the **Solution Explorer**, double-click **License** in the **SYSTEM** subtree.



 \Rightarrow The TwinCAT 3 license manager opens.

5. Open the **Manage Licenses** tab. In the **Add License** column, check the check box for the license you want to add to your project (e.g. "TF6420: TC3 Database Server").

Order Information (Runtime) M	anage Licenses Project Licenses Online Licenses		
Disable automatic detection	n of required licenses for project		
Order No	License	Add License	•
TF6310	TC3 TCP/IP	cpu license	
TF6311	TC3 TCP/UDP RT	cpu license	
TF6340	TC3 Serial-Communication	cpu license	
TF6350	TC3 SMS-SMTP	cpu license	
TF6360	TC3 Virtual-Serial-COM	cpu license	
TF6420	TC3 Database-Server	Cpu license	

- 6. Open the Order Information (Runtime) tab.
 - ⇒ In the tabular overview of licenses, the previously selected license is displayed with the status "missing".

TwinCAT SampleProject 🕆 🗙							
Order Information (Runtime) Manage Licenses Project Licenses Online Licenses							
License Devic	e Target (Hardware Id)		▼ Add				
System Id:		P	latform:				
E13751F7-79E	39-4063-416C-615ED53FA7BD	C	other (90)	•			
License Reque	st						
Provider:	Beckhoff Automation	•	Generate File				
License Id:		Customer Id:					
Comment							
License Activat	ion						
71	Days Trial License	Lice	ense Response File				
Order No	License	Instances	License TAN	Current Status	License Id		
TC1200	TC3 PLC	cpu license		expires on Jul 7, 2018 (trial license)	66689887-CCBD-452C-AC9A-039D997C6E66		
TF6420	TC3 Database-Server	cpu license		missing	92583661-35AE-45CE-BD4F-C35BFE16F07E		
TF6710	TC3 IoT Functions	cpu license		expires on Jul 7, 2018 (trial license)	2149932B-0B77-4004-B43F-E85CEEFF347D		

7. Click 7-Day Trial License... to activate the 7-day trial license.

vinCAT SampleProject 🤫 🗙						
Order Information (Runtime) Manage Licenses Project Licenses Online Licenses						
License Device Target (Hardware Id)						
System Id:		PI	atform:			
E13751F7-79	B9-4063-416C-615ED53FA7BD	0	ther (90)	•		
License Reque	est					
Provider:	Beckhoff Automation	▼	Generate File			
License Id:		Customer Id:				
Comment:						
License Activa	tion					
7	Days Trial License	Lice	nse Response File			
Order No	License	Instances	License TAN	Current Status	License Id	
TC1200	TC3 PLC	cpu license		expires on Jul 11, 2018 (trial license)	66689887-CCBD-452C-AC9A-039D997C6E66	
TF6420	TC3 Database-Server	cpu license		expires on Jul 11, 2018 (trial license)	92583661-35AE-45CE-BD4F-C35BFE16F07E	
TF6710	TC3 IoT Functions	cpu license		expires on Jul 11, 2018 (trial license)	2149932B-0B77-4004-B43F-E85CEEFF347D	

- \Rightarrow A dialog box opens, prompting you to enter the security code displayed in the dialog.
- 8. Enter the code exactly as it appears, confirm it and acknowledge the subsequent dialog indicating successful activation.
 - \Rightarrow In the tabular overview of licenses, the license status now indicates the expiry date of the license.
- 9. Restart the TwinCAT system.

 \Rightarrow The 7-day trial version is enabled.

4 Analytics Workflow - First Steps


This step by step documentation presents the complete TwinCAT Analytics workflow. From the data acquisition over the communication and historizing up to the evaluation and analysis of the data and to the presentation of the data in web-based dashboard.

4.1 Recording data from the machine


On the machine side is the Analytics Logger the recorder of process data from the machine image, PLC, NC and so on. The Logger is working in the real-time context of TwinCAT.

The TwinCAT Analytics Logger is installed with TwinCAT XAE and XAR. The Logger can act as MQTT Client to communicate the recorded data to a native MQTT Message Broker or store the data in the same data format in a local binary file. By the usage as MQTT Client the Logger is able to bypass short disconnects to the Message Broker with a ring buffer functionality. You can configure a ring buffer as well for the local binary file storage.

• To configure the Analytics Logger you have to navigate in your existing TwinCAT Project to the Analytics tree node



• Right click on this node and click on "Add Data Logger" to add one new instance to your configuration



• For configuring the base settings, please double click on the new tree item

MeasurementSamplePLC - TcXaeShell File Edit View Project Build Debug TwinCAT TwinSAFE PLC Team Scope Tools Window Help Image: Im					
Solution Explorer 🔹 🖣 🗙	MeasurementSamplePLC 😐 🗙 Variable				
© ⊙ 🟠 🛱 ▼ 💿 ▼ 🗊 🖌 💻 Search Solution Explorer (Ctrl+ü)	Parameter (Init) TLS				
Solution 'MeasurementSamplePLC' (1 project)	Name	Value	CS	Туре	
Solution MeasurementSamplePEC (Tproject) MeasurementSamplePEC	Data Format	ANALYTICS_FORMAT_FILE		ANALYTICS_FORMAT	
SYSTEM	Data Compression	ANALYTICS_COMPRESSION_RL		ANALYTICS_COMPRESSION	
MOTION	Max. Compression Compare Width	ANALYTICS_COMP_WIDTH_1		ANALYTICS_COMPRESSION_WIDTH	
PLC	MQTT Host Name	127.0.0.1		STRING(80)	
ScopeSample	MQTT Tcp Port	1883		UINT	
 Image: ScopeSample Project Image: ScopeSample Instance 	MQTT Main Topic	DefaultMainTopic		STRING(255)	
Scopesariple instance PicTask inputs	MQTT Client ID			STRING(80)	
(3) SAFETY	MOTT User Name			STRING(255)	
₩. C++	MQTT Password			STRING(80)	
ANALYTICS	MQLEFFassword			3111140(00)	
Data Logger 1					
Þ 🔽 I/O					

You can make your specific Analytics Logger settings

-Data Format: Binary file or MQTT stream

-FILE format: Analytics Logger stores the data in local binary files and all other settings are not necessary anymore. The files will be stored in C:\TwinCAT\3.1\Boot\Analytics.

-BINARY: Data will be sent to the configured MQTT Message Broker. You can have multiple Logger in one TwinCAT project to communicate data to different MQTT Message Broker.

-Data Compression: on (default) or off

-Max Compression: mode of the compression

-MQTT host name

-MQTT Tcp port

-MQTT main topic for own hierarchical levels to keep the identification easy


-MQTT Client ID should be unique in the network

-MQTT username

-MQTT password to make authentication at the message broker

-At the TLS (Transport Layer Security) tab, security settings can be configured. TLS is a secure communication channel between client and server. By the usage of certificates, the TCP port 8883 is exclusively reserved for MQTT over TLS. Analytics Logger is supporting the modes CA Certificates, CA Certificates & Client Certificate and Preshared Key (PSK) mode.

• If variables in your PLC application are marked in the declaration with the attribute {attribute 'TcAnalytics'} they will be shown automatically as a stream below the Data Logger tree node.



An additional device stream will be shown if your configuration provides an EtherCAT Process Image.

· In the stream a Selection tab is available to choose the variables that should be recorded


🖁 🕒 🗢 🗧 📩 🖕 🔛 🖉 🖁 🕹 🗗 白ーク	AT TwinSAFE PLC Team Scope Tools Window Help • • • Release • TwinCAT RT (x64) • • Attach • • • • • • • • • • • • • • • • • • • •
Solution Explorer 🔹 👎 🗙	MeasurementSamplePLC + × Variables MAIN
○ ○ ☆ ☆ マ ○ マ ○ ▲ ▲ Search Solution Explorer (Ctrl+ü)	Online Selection Data Handling
 Solution 'MeasurementSamplePLC' (1 project) MeasurementSamplePLC SYSTEM MOTION PLC ScopeSample ScopeSample Project ScopeSample Instance SAFETY C++ ANALYTICS Data Logger 1 VO 	Stream Source: ScopeSample.ScopeSample Instance.PIcTask PIcTask Inputs MAIN b TerminalIn Other PicTask Internal Variables fAM Variables fPeak Variables fPeak Variables fSuster Variables fSuster Variables fSine Variables fSine Variables fStairs Variables fTriangular

• Finally it is possible to change the package size for the frames or to configure the ring buffer for disconnects and file in the Data Handling tab.

MeasurementSamplePLC - TcXaeShell	
File Edit View Project Build Debug TwinC	AT TwinSAFE PLC Team Scope Tools Window Help
💿・〇 粉・白・😩 🗎 📲 よ ご 白 ク	- C - Release - TwinCAT RT (x64) - Attach
🔋 Build 4024.0 (Loaded) 💿 👻 📮 👬 🌆 🛛 🜌 🛷 🔨 🤇	🗑 🍖 🐔 MeasurementSamplePLC 🔹 <local> 🔹 🛫</local>
Solution Explorer 👻 🖣 🗙	MeasurementSamplePLC 🗢 🗙 Variables MAIN
© © 🏠 🛱 • To • 🗗 🌶 🗕	Online Selection Data Handling
Search Solution Explorer (Ctrl+ü)	Data Size: (Bytes)
 Solution 'MeasurementSamplePLC' (1 project) MeasurementSamplePLC 	Max ADS Buffer: 32 🔹 3 (KB) 32 ms
SYSTEM	Max File Size: 256 577 (KB) 8.192 s
	Sampling Divider: 1
CopeSample	Autostart Stream: 🔽
GropeSample Project ScopeSample Instance	Ring Buffer
SAFETY	File Count: 2 🚖 1153 (KB) 16.384 s
 ANALYTICS A Data Logger 1 	Queue messages when disconnected
	Store in file
Þ 💆 1/0	Queue Size: 0 (KB)

4.2 Communication

Currently, the Analytics workflow is fully mappable via MQTT. The engineering tools can also access the data of the machines via ADS and carry out analyzes.



If you choose for the IoT communication protocol MQTT you have to setup a native MQTT Message Broker somewhere in the network (VM in a cloud system is also possible). This Message Broker provides a decoupling of the different applications in the Analytics Workflow.

4.3 Historicize data

After installation of the TwinCAT Analytics Storage Provider you are able to configure the service running in the background. You will find therefore the TcAnalyticsStorageProvider_Config application in the folder C: \TwinCAT\Functions\TF3520-Analytics-StorageProvider\WinService.

🛃 TwinCAT Analyti	ics Storage Provider Configuration	×
Analytics Storage MainTopic: Comment:	Provider Beckhoff/ TcASP@PASCALD-NB03	
Messagebroker — Settings	Set connection settings for message broker	
Storage Type: Connectionstring:	AnalyticsFile Analytics Folder	
C:\TwinCAT\Ft \WinService\	unctions\TF3520-Analytics-StorageProvider Storage	
-	Additional Properties	
Analytics Storage Analytics Storage Automatic	Provider Windows Service Image: Start Stop Image: Start Stop	
	Cancel Save Config OK	

The main part of the topic can be set in the configuration as well as the comment which will be used for identification if more than one Storage Provider is registered at the Message Broker.

Connection Settings			×
Broker:	172.17.62.145		
User:	Pwd:	Port:	1883
Certificate			
CA:			
Cert:			Pwd:
Key:			
Check Settings			ок

You are able to provide the Message Broker settings and to decide for storage type:

- Analytics File (binary file)
- Microsoft SQL
- Microsoft Azure Blob (Azure Cloud necessary)

Finally, you can save the config and start the service. The next step is the configuration of the specific record. Therefore you should choose in your development environment the Storage Provider Recorder.

TwinCAT TwinCAT HMI TwinSAFE PLC Team	Scope Tools Window Help
🛯 🗶 Software Protection	
Show Realtime Ethernet Compatible Devices	
File Handling •	
EtherCAT Devices	
CProjectCompare	Networks
ADS Monitor	
Target Browser	
Analytics +	🛠 New Network
Filter Designer •	🐺 Deploy Runtime
About TwinCAT	Storage Provider Recorder
TwinCAT	Analytics Storage Provider Recorder 🔹 🔍 🗙
P @	- I 🔘 🝸 🗮 📓 RecorderAlias:
Disconnec	ated and a set of the

The recorder has also to connect to the Message Broker. So you have to provide the same settings as for the background service.

TwinCAT Analytics Storage Provider Recorder					. ▲	×
P @	• 0 Y =	🗧 🍟 🎬 RecorderAlias:				
	Connection Settin	ngs		X	1	
	Broker:	172.17.6	2.145			
	User:	Pwd:	Port: 1	1883		
	🔲 Certificate					
	CA:					
	Cert:			Pwd:		
	Key:					
	Check Setting	3		OK		
				i.		
Disconnected						

After this you can click to icon with the small cloud to search Storage Providers at the configured Message Broker. Here you will find also the comment you gave already by the service configuration to identify your Storage Provider.

in CAT Analytics Storage Provider Recorder 🗾 👻 🗉	X
👂 💩 🔽 🔽 📔 🕲 🝸 🖉 🖉 🖉 🖉 RecorderAlias:	
TwinCAT Analytics Storage Provider Windows Service	
sconnected	

The configuration of the record is very easy. You have just to choose your target in the Target Browser. Click on Live data and choose one or more variables by multiselect and put them by drag and drop to the recorder window.

	age Provider Recorder							- 🗆 ×	
🔑 🐵 TwinCAT Ana	alytics Storage Provider Windows Servic	• 0 Y = 🍇	📋 🛛 Record	erAlias:					
Recording	g		Duration	Start Timestam	np RingBuffer				
	4								
	-71								
	/								
	/								
	/								
	/								
B-ID: 22556078-7844-4f75-b0d6-8ce66dde2afe Connected to "172_7.62	2.145" 🔄 -								
rget Browser ADS TcDBSvv TcAnalytics TcAnalytics File Opcia	Enter Filter								
ADS TcDBSrv TcAnalytics TcAnalytics File Opcia									
부 책 집 / 奈	Variables > fStairs >		_						
6 172.17.62.145	Name	Type	Size		III-Name Comment	Subitems Unit	Bit-Offset	Attributes (Instance)	
-									
 TestSignals 	■ @aBufferPulse	ARRAY [110]	80	Array V	ariables	10	1696	none	none
✓ ■ TestSignals	🗷 🞯 aBufferSawtooth	ARRAY [110]	80	Array Vi Array Vi	ariables	10	1696 3616	none	none none
∡ → Live Data	■ 圖aBufferSawtooth ■ 圖aBufferSine	ARRAY [110] ARRAY [110]	80 80	Array Vi Array Vi Array Vi	ariables ariables	10 10	1696 3616 4256	none none	none none none
 Live Data TestSignals/StreamFastCompressed_Wdth8 	● 劒aBufferSawtooth ● 劒aBufferSine ● 劒aBufferSquare	ARRAY [110] ARRAY [110] ARRAY [110]	80 80 80	Array Va Array Va Array Va Array Va	ariables ariables ariables	10 10 10	1696 3616 4256 4896	none none none	none none none none
 Live Data TestSignals/StreamFastCompressed_Wdth8 TestSignals/StreamFastCompressed_Wdth32 	● 鋼aBufferSawtooth ● 鋼aBufferSine ● 鋼aBufferSquare ● 鋼aBufferStairs	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110]	80 80 80 80	Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi	ariables ariables ariables ariables	10 10 10 10	1696 3616 4256 4896 2976	none none none none	none none none none none
 > Live Data TestSignals/StreamFastCompressed_Wdth8 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast 	● 個aBufferSawtooth ● 個aBufferSine ● 個aBufferSquare ● 個aBufferStairs ● 個aBufferTriangular	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110]	80 80 80 80 80	Array Va Array Va Array Va Array Va Array Va Array Va Array Va	ariables ariables ariables ariables ariables	10 10 10	1696 3616 4256 4896 2976 5536	none none none none none	none none none none none none
 Live Data TestSignals/StreamFastCompressed_Width8 TestSignals/StreamFastCompressed_Width32 TestSignals/StreamFast Michional Data 	 ● 鋼 aBufferSawtooth ● 鋼 aBufferSine ● 鋼 aBufferSquare ● 鋼 aBufferStairs 	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110]	80 80 80 80	Array Va Array Va Array Va Array Va Array Va Array Va Array Va Primitive Va	ariables ariables ariables ariables	10 10 10 10	1696 3616 4256 4896 2976	none none none none	none none none none none
 Live Data TestSignals/StreamFastCompressed_Wdth3 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast EtstSignals/StreamFast Withincal Data VisionApp 	● 個aBufferSawtooth ● 個aBufferSine ● 個aBufferSquare ● 個aBufferStairs ● 個aBufferTriangular	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] BOOL	80 80 80 80 80 1	Array V: Array V: Array V: Array V: Array V: Array V: Array V: Primitive V: Primitive V:	ariables ariables ariables ariables ariables ariables	10 10 10 10	1696 3616 4256 4896 2976 5536 344	none none none none none	none none none none none none
 Live Data TestSignals/StreamFastCompressed_Wdth8 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast Historical Data VisionApp ge682ze6-b654-0881-2375-de8123db1beb 	BufferSawtooth BalufferSawtooth BalufferSine BalufferSine BalufferStairs BalufferStairs BalufferTriangular BbEdge BMtferTriangular	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] BOOL BOOL	80 80 80 80 80 1 1	Array V: Array V: Array V: Array V: Array V: Array V: Array V: Primitive V: Primitive V: Primitive V:	ariables ariables ariables ariables ariables ariables ariables	10 10 10 10	1696 3616 4256 4896 2976 5536 344 336	none none none none none none	none none none none none none none
 Live Data TestSignals/StreamFastCompressed_Wdth8 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast Historical Data VirionApp cec82eee-b654-0881-2375-de8123db1beb ccc0276-4286-8745-c7d4-a24eb4f33d9c 	BalufferSawtooth BalufferSine BalufferSine BalufferSine BalufferSine BalufferSine BalufferSine BalufferSine BalufferTriangular BibMqtEvent BibMqtEvent BifAM	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] BOOL BOOL LREAL	80 80 80 80 1 1 8	Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi	ariables ariables ariables ariables ariables ariables ariables ariables.f	10 10 10 10	1696 3616 4256 4896 2976 5536 344 336 544	none none none none none none none	none none none none none none none none
	BufferSantooth BaldferSine BaldferSine BaldferSine BaldferSine BaldferSine BaldferSine BaldferSine BaldferBild BaldferDissen Bald	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] BOOL BOOL LREAL LREAL	80 80 80 80 1 1 8 8	Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi	ariables ariables ariables ariables ariables ariables ariables.f ariables.f	10 10 10 10	1696 3616 4256 2976 5536 344 336 544 416	none none none none none none none none	none none none none none none none none
Live Data TestSignals/StreamFastCompressed_Wdth3 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast WithionApp C6682ee6-b654-0881-2375-de8123db1beb Tacc072f-428f-8745-c7d4-824eb4733d9c Tedef25fo-c130-7d7e-0a26-71ed8cee9340 Bigl40	BuffreiSantoch BuffreiSantoch BuffreiSantoch BuffreiSant BissefferTinangular	ARRAY [110] ARRAY [110] ARRAY [110] ARRAY [110] BOOL BOOL LREAL LREAL LREAL	80 80 80 80 1 1 8 8 8 8 8	Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi	ariables ariables ariables ariables ariables ariables.f ariables.f ariables.f ariables.f ariables.f	10 10 10 10	1696 3616 4256 4896 2976 5536 344 336 544 416 608	none none none none none none none none	none none none none none none none none
Live Data TestSignals/StreamFastCompressed_Wdth8 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast Historical Data VioinApp Comparison of the stream of the	(# @BuffretSantooth (# @BuffretSantooth (# @BuffretSantooth (# @BuffretSantooth (# @BuffretSantooth (# @BuffretTrangular (# @BuffretSantooth (# @BuffretSantoot	ARRAY [1.10] ARRAY [1.10] ARRAY [1.10] ARRAY [1.10] BOOL BOOL LREAL LREAL LREAL LREAL LREAL LREAL LREAL	80 80 80 80 1 1 8 8 8 8 8 8 8 8 8 8 8 8	Array Vi Primitive Vi	ariables ariables ariables ariables ariables ariables.f ariables.f ariables.f ariables.f ariables.f ariables.f	10 10 10 10	1696 3616 4256 2976 5536 344 336 544 416 608 672 352 736	none none none none none none none none	none none none none none none none none
Live Data TestSignals/StreamFastCompressed_Wdth3 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFastCompressed_Wdth32 TestSignals/StreamFast VisionApp VisionApp Tarcor2148:P8755-c714-b24b.4473d9c Trac4724.488:P875-c714-b24b.4473d9c The47250-c130-7d7e-0a26-71ed8ce49340 Big40 Jisiddede=4fea-78d2-9ac1-65101d0006677 Jisiddede=4fea-78d2-9ac1-65101d0006677 Jisidfoec6-3ab5-c1cc-1a1d-e6f4da86adf0 SetTestSignals/StreamFast	 ④ 御 SufferSawtooth ● 御 SufferSine ● 御 SufferSine ● 御 SufferSine ● 御 SufferTriangular 御 SufferTriangular 御 SufferTriangular 御 FAM ● forowSlow ● ff Pulse ● ff Pulse ● ff Pulse ● ff Pulse ● forowSlow ● forowSlowSlow ● forowSlow ●	ARRAY [1.10] ARRAY [1.10] ARRAY [1.10] ARRAY [1.10] BOOL BOOL LREAL LREAL LREAL LREAL LREAL LREAL LREAL LREAL	80 80 80 80 80 1 1 8 8 8 8 8 8 8 8 8 8 8	Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Array Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi Primitive Vi	ariables ariables ariables ariables ariables ariables.f ariables.f ariables.f ariables.f ariables.f ariables.f ariables.f	10 10 10 10 0 0 0 0 0 0 0 0 0 0 0 0 0 0	1696 3616 4256 2976 5536 344 336 544 416 608 672 352 736 800	none none none none none none none none	none none none none none none none none
Live Data TetSignals/StreamFastCompressed_Wdth8 TetSignals/StreamFastCompressed_Wdth32 TetSignals/StreamFast Withorical Data Visionciap Ge862ee6-b654-0801-2375-de8123db1beb Tacc0724-428-8745-c7d4-824eb4733d9c Tot4250-c134-e326-b1e38d9c Jig40 di80ddde=afea-7842-9ac1-6511d000687	(# @BuffretSantooth (# @BuffretSantooth (# @BuffretSantooth (# @BuffretSantooth (# @BuffretSantooth (# @BuffretTrangular (# @BuffretSantooth (# @BuffretSantoot	ARRAY [1.10] ARRAY [1.10] ARRAY [1.10] ARRAY [1.10] BOOL BOOL LREAL LREAL LREAL LREAL LREAL LREAL LREAL	80 80 80 80 1 1 8 8 8 8 8 8 8 8 8 8 8 8	Array Vi Primitive Vi	ariables ariables ariables ariables ariables ariables.f ariables.f ariables.f ariables.f ariables.f ariables.f	10 10 10 10	1696 3616 4256 2976 5536 344 336 544 416 608 672 352 736	none none none none none none none none	none none none none none none none none

The recorder will ask you if you like to add just the chose variables or the complete source process image of the variables.

Add Recording				×
TestSignals/StreamFast				
Topic Alias:	Record Name:	Record D		
LongTimeMachineObs	Rec_1	0 🚔	Hours 0 🚔 Minute	s
Store Subset of Symbols	process image			
Name		BaseType	BitOffset	
Variables.fSine Variables.fStairs		LREAL LREAL LREAL	608 800 928	
Ringbuffer: None		Cancel	Add	

You can also configure record names and a duration (otherwise endless until manual stop). A ringbuffer can be set by memory or time.

	Recording	Duration	Start Timestamp	RingBuffer	
iart	LongTimeMachineObs: ("TestSignals/StreamFast")	infinite		None	

Click the Start button to start the record. After this you can also disconnect the recorder, because the background service do the work. It is also possible that someone else connect to this Storage Provider service and control the running record.

		nalytics Storage Pri								→ □ ×
	₽ @ T	winCAT Analytics	Storage Provider Windows S	ervic 🔹 🚺 🍸	🗏 潅 🎽 Recor	derAlias:				
		Recording			Duration	Start Timestamp	RingBuffer			
	STOP	LongTimeMach	hineObs: ("TestSignals/Strea	nFast")	infinite	08.11.2019 14:35:28	None			
	-									
	-									
	-									
	-									
			_							
1556078-7844-4F75-b0d6-8ce66dde2afe	Connected	to "172.17.62.145"	<u>e</u> -							
	Connected	to "172.17.62.145"	2							
vauser										
wser TcDBSrv <mark>TcAnalytics</mark> TcAnaly		to "172.17.62.145" cUa	Enter Filter							.≓ Filter Ednor⊷ ▼ ×γ
wser TcDBSrv <mark>TcAnalytics</mark> TcAnaly			Enter Filter Variables > fStairs >	Tat	Č	Catalog - Euli Mar		Subiner Heb		4 Today
wser TcDBSrv <mark>TcAnalytics</mark> TcAnaly ❷			Enter Filter Variables > fStairs > Name	Туре	Size		e Comment	Subitems Unit	Bit-Offset Att	▲ Today
wser TcDBSrv <mark>TcAnalytics</mark> TcAnaly ڬ 🏕 🤁 172.17.62.145			Enter Filter Variables > fStairs > Name		Size 0 8	Struct Variables		Subitems Unit 3	0 no	▲ Today A Today A Ret 1 (>56 s) [2019-11-08 16:29:42.785, 2019-11-08 16:30:39.484]
xxser TcD8Sv <mark>TcAnalytics</mark> TcAnaly © ♪ ✿ 172.17.62.145 ¶ TestSignals			Enter Filter Variables > fStairs > Name	Type LREAL LREAL	0		f	3	0 no 0 no	▲ Today Rec_1 (>56 s) [2019-11-08 16:29:42.785, 2019-11-08 16:30:39,484] StartTime EndTime
wser TcDBSv TcAnalytics TcAnaly D & 172.17.62.145 TextSignals → Live Data			Enter Filter Variables > fStairs > Name ■ (⊕ Variables @ fPeak	LREAL	0	Struct Variables Primitive Variables	f f	3	0 no 0 no	 Today Rec, 1 (>56 s) [2019-11-08 15:29:42.785, 2019-11-08 15:30:39.484] StartTime EndTime 2019-11-08 15:30:27.134
wser TcDBSv TcAnalytics TcAnaly D & 172.17.62.145 TextSignals → Live Data	rtics File Op	cUa	Enter Filter Variables > fStairs > Name ■ (a) Variables (@ fPeak @ fSine	LREAL LREAL	0 8 8	Struct Variables Primitive Variables Primitive Variables	f f	3 0 0	0 no 0 no 64 no	 Today Rec, 1 (>56 s) [2019-11-08 15:29:42.785, 2019-11-08 15:30:39.484] StartTime EndTime 2019-11-08 15:30:27.134
wser TcDBSv TcAnalytics TcAnaly © ≠ Ø 172.17.62.145 Tetstiganals → Live Data ← Historical Data	rtics File Op	cUa	Enter Filter Variables > fStairs > Name ■ (a) Variables (@ fPeak @ fSine	LREAL LREAL	0 8 8	Struct Variables Primitive Variables Primitive Variables	f f	3 0 0	0 no 0 no 64 no	▲ Today Rec.1 (>56.6) (2019-11-08.15:25:42.705, 2019-11-08.16:30:33.464) Sastimme 2019-11-08.16:29:42.705 Conditional Condi Conditi Condi Condi Conditional Conditional Condi Condi Condi
wser TcDBSv TcAnalytics TcAnaly © ≠ ✿ 172.17.62.145 ↓ Eve Data ■ Elechtof/TcAnalyticsStorage ■ Betchtof/TcAnalyticsStorage	rtics File Op	cUa	Enter Filter Variables > fStairs > Name ■ (a) Variables (@ fPeak @ fSine	LREAL LREAL	0 8 8	Struct Variables Primitive Variables Primitive Variables	f f	3 0 0	0 no 0 no 64 no	▲ Todey
TcDBSvv TcAnslytics TcAnsly Image: Total and the state of the state	rtics File Op	cUa	Enter Filter Variables > fStairs > Name ■ (a) Variables (@ fPeak @ fSine	LREAL LREAL	0 8 8	Struct Variables Primitive Variables Primitive Variables	f f	3 0 0	0 no 0 no 64 no	▲ Today Rec.1 (>56.6) (2019-11-08.15:25:42.705, 2019-11-08.16:30:33.464) Sastimme 2019-11-08.16:29:42.705 Conditional Condi Conditi Condi Condi Conditional Conditional Condi Condi Condi
Avver TCDBSvv TcAnalytics TcAnaly Classifier States TextSignals Historica Data ExcHanglis ExcHanglis ExcHanglis ExcHanglis ExcHanglis Data ExcHanglis	rtics File Op	cUa	Enter Filter Variables > fStairs > Name ■ (a) Variables (@ fPeak @ fSine	LREAL LREAL	0 8 8	Struct Variables Primitive Variables Primitive Variables	f f	3 0 0	0 no 0 no 64 no	▲ Today Rec.1 (>56.6) (2019-11-08.15:25:42.705, 2019-11-08.16:30:33.464) Sastimme 2019-11-08.16:29:42.705 Conditional Condi Conditi Condi Condi Conditional Conditional Condi Condi Condi
	rtics File Op	cUa	Enter Filter Variables > fStairs > Name ■ (a) Variables (@ fPeak @ fSine	LREAL LREAL	0 8 8	Struct Variables Primitive Variables Primitive Variables	f f	3 0 0	0 no 0 no 64 no	▲ Today Rec.1 (>56.6) (2019-11-08.15:25:42.705, 2019-11-08.16:30:33.464) Sastimme 2019-11-08.16:29:42.705 Conditional Condi Conditi Condi Condi Conditional Conditional Condi Condi Condi

After and also during the record you can choose the historical data as input for your analysis in the Target Browser. In the Target Browser you will find for historical data a new control on the right hand site. There you can choose the time span for your data.

4.4 Analyse data

Open your TwinCAT engineering environment to start the analysis of the data.

Open Visual Studio® >> File >> New >> Project...

Choose from TwinCAT Measurement the Analytics project template.

New Project						?	×
Recent		Sort by: Defa	ult 🔹 🏭		Search (Ctrl+E)		P
 Installed 		Arvin. Emp	ty Measurement Project	TwinCAT Measurement	Type: TwinCAT Measureme		
 TwinCAT Measure Analytics Work Bode Plot 			surement Wizard	TwinCAT Measurement	Creates a Measurement Proje Analytics Project	ect with	a ne
FilterDesign Scope	er	TY S	cope Project	TwinCAT Measurement			
TwinCAT Projec TwinCAT PLC	cts	The second secon	cope Project	TwinCAT Measurement			
TwinCAT Connector TcXaeShell Solu		TY 🐨	IC Scope Project	TwinCAT Measurement			
		Digi	tal Scope Project	TwinCAT Measurement			
		Sing	leBar Scope Project	TwinCAT Measurement			
		Arra	yBar Scope Project	TwinCAT Measurement			
		R Ana	lytics Project	TwinCAT Measurement			
		Here Bod	e Plot	TwinCAT Measurement			
-	t you are looking for? I Studio Installer	Filte	r Designer Project	TwinCAT Measurement			
<u>N</u> ame:	TwinCAT Measurer	ment Project1					
Location:	C:\Users\Documer	nts\TcXaeShell		•	Browse		
Solution na <u>m</u> e:	TwinCAT Measurer	ment Project1			 Create <u>directory</u> for solution Add to So<u>u</u>rce Control 		
				[Add to So <u>u</u> rce Control	Ca	n

The new project will be shown in the Solution Explorer. After a click on the Analytics Project tree node item a start window opens where you can select your first action. From here, you can add a Network, open the Toolbox, open the Target Browser or open the Analytics Storage Provider Recorder. You will do all these actions in the following steps.

TwinCAT Measurement Project10 - TcXaeShell		💎 🗗 Quick Launch (Ctrl+Q) 🛛 🔎 💶 🗙
File Edit View Project Build Debug TwinCAT Th	winSAFE PLC Team Scope Tools Window Help	
0-0 8-1-1 H + K 0 1 9-0.	- Debug - TwinCAT CE7 (ARMV7) - 🕨 Attach 🍺 - 🗊 🗜 🗊 🗰 🎕 🕐 🖸 - 📑 🖗 🖓 😳 -	
Build 4024.0 (Loaded)		
		▼ Toolbox ▼ 4 ×
	Analytics Project 🕫 🗙	Toolbox
○ ○ ☆ ☆ - 'o - ♂ / ≯ -		Threshold String Classificator 1Ch
Search Solution Explorer (Ctrl+ü)		State Histogram 1Ch
Solution 'TwinCAT Measurement Project10' (1 project)	TE3500 TwinCAT Analytics Workbench	Bandwidth Classificator 1Ch
WinCAT Measurement Project10 Analytics Project	Vorkberch-ID: c0bdfe77-e50-467-a2a-b9276523d997	Time Based Envelope 1Ch
Network 1		Histogram 1Ch
Inputs		Bandwidth Classificator 3Ch
	add a Network.	Curve Sketcher 1Ch
	Add a Network or select an existing from the Solution Explorer to open the Network editor tab.	Section Timer 1Ch
		Analytics - Compare
	open the Toobbox.	Ne Pointer
	Drag Analytics-Functions to a Network editor and configure or extend a project.	A Numerical Compare 1Ch
	add referenced Scope.	Numerical Compare 2Ch
	Create a new TC3 Scope file, which contains all Analytics variables to show them.	& Logic Operation Counter
	encare a new new second enclosed and an enables to show another	*X Detect String Change 1Ch
	open the Target Browser.	*X String Compare 1Ch
	Drag Analytics variables from the Target Browser to the inputs of the Analytics-Functions to add an InputStream to the project.	*X String Compare 2Ch
		‡+ Multiplexer
	open the Analytics Storage Provider Recorder	Analytics - Math Pointer
	Use the Analytics Storage Provider Recorder to manage connections to a Storage Provider and configure records.	Integrator 1Ch
		Math Operation
	deploy Runtime. Once an Analysis is designed and tested in the Workbench, autogenerated code can be compiled and deployed to an Analytics-Runtime-System.	Slope Analysis 1Ch
	Unce an Analysis is designed and tested in the Workbench, autogenerated code can be complied and deproyed to an Analytics-Runtime-system.	Ta Math Operation 1Ch
	First Steps.	Analytics - Training Base
	Launch the documentation to get detailed information about how to start into TwinCAT Analytics.	Pointer
		Time Based Teach Path 1Ch
		Analytics - XTS
		Pointer
		XTS Distance Integrator 1Ch
		 XTS Velocity Analysis 1Ch
		 XTS Acceleration Analysis 1Ch
		Analytics - WT
		WT Turbulence 1Ch
I I		Analytics - XY Path Analysis
I I		Pointer
		XY Gate Monitor 2Ch
		XY Shape Monitor Circle 2Ch
Solution Explorer Team Explorer		🕷 water bet in a state 🛛 📉
Target Browser Cross Reference List Error List Output		
CT Durks		

It makes sense to open in a first step the Toolbox of Visual Studio[®]. There you will find all the supported algorithm of TwinCAT Analytics. Algorithm must be organized and grouped into networks. Right click on the Analytics Project to add a new Network or add a Network using the start page. The first Network is always generated by default.

WinCAT Measurement Project10 - TcXaeShell File Edit Yiew Project Build Debug TwinCAT 1 Solution 1 Solution 1 Solution 1	TwinSAFE PLC Tea <u>m</u> Scope Iools <u>Wi</u> ndow <u>H</u> elp	Quick Launch (Ctrl+Q)
Build 4024.0 (Loaded)		
Elle Edit View Project Build Debug TwinCAT T ◎ • ◎ 劉 • ʿ□ • ்⊒ ⊯ 🔐 🖁 ♂ ♂ ♂ ♥	NwiSAFE PLC Team_Scope Iools Window Help - Debug - TwinCAT CE7(ABM/7) - ▶ Attach 声声 - 一戸 ▶ = 戸 ▶ =	Ibobox • J × Search Foolbox Ø × Secons Stackter 1Ch Image: Stackter 1Ch Analytics - Compare Nonercial Compare 1Ch Analytics - Compare 1Ch Analytics - Compare 1Ch Nonercial Compare 1Ch Stang Compare 1Ch Nonercial Compare 1Ch Stang Compare 1Ch Nonercial Compare 1Ch Stang Compare 1Ch Stang Compare 1Ch Stang Compare 1Ch Multiplexer Analytics - Math Pointer Integrator 1Ch Multiplexer Analytics - Math Pointer Image 1Ch Multiplexer Analytics - Math Norther Fointer Integrator 1Ch Analytics - Math Norther NTS Academical Relaysits (Ch Analytics - WT Norther Norther Norther NTS Norther Analytics (Ch Analytics - WT Norther Norther Norther Norther
		Xing Signal S - A Featuring as Pointer XV Gate Monitor 2Ch XV Shape Monitor Circle 2Ch XV Shape Monitor Rectangle 2Ch XV Shape Monitor Triangle 2Ch General
Solution Explorer Team Explorer	WB-ID: clbsdse77-e2b6-4e67-e2ac-b927a522d997	There are no usable controls in this group. Drag an item onto this text to add it to the toolbox.
Target Browser Cross Reference List Error List Output		Add to Source Control 1

If you click on the Network an editor will be open. Now you can take the algorithm you like by drag and drop into the editor surface. After choosing the algorithm you need to connect input variables to the modules (algorithm). Therefor open the Target Browser.

TwinCAT >> Target Browser >> Target Browser

		TwinCAT Measurement Project10 - TcXaeShell	
	File	le Edit View Project Build Debug TwinCAT TwinSAFE PLC Team	Scope Tools Window
		😣 Software Protection 🕴 - Debug - Twind	CAT CE7 (ARMV7) 🔹 🕨
		Show Realtime Ethernet Compatible Devices 🔞 🐾 🌾	*
ſ		File Handling	s Project
ł		EtherCAT Devices	stroject
	$\langle \! \! 0 \rangle$	TcProjectCompare	
		Database Server	
		Target Browser Target Browser Target Browser	
		Analytics 🕨 🖉 Clear Error List	
		Filter Designer	-
	_	About TwinCAT	

Choose now the TcAnalytics or TcAnalyticsFile tab in the Target Browser. We go ahead with the TcAnalytics tab (MQTT). Click on the green marked icon in the toolbar of this Analytics extension. A window will be open where you can provide your Message Broker connectivity data.

Target Browser						Conr	nection Settings			>	×
ADS	TcDBSrv	TcAnalytics	TcAnalytics File	OpcUa	Enter Filter		,				
						Broker:		MyBroker			
÷ ī ī ₩ ° ₩ Ţ					▼ Name	User:	Pwd	:	Port:	1883	
						Certif	ïcate				
						CA:					
						Cert:				Pwd:	
						Kev:					
						Check	Config		Cancel	ОК	
Target Br	owser Cros	s Reference List	Error List Output								

Choose your MQTT Analytics client (TwinCAT Analytics Logger, TwinCAT IoT Data Agent or Beckhoff EK9160). For each controller you have a unique ID. This ID is shown in the Target Browser. Not very legible, of course. Therefore, click on the icon with the gear to get to the machine administration page. Here you can provide a System Alias name which is shown in the Target Browser instead of the GUID.

Machine Administration								-	
*# *# • `									
Source	Customer	SystemID	System Alias	Online	Position	Topic Alias	Description		
• 172.17.62.145		•		•	•	•		^ Colu	mns iource
TwinCAT Analytics Logger	MA Laser	3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True					ource Customer
TwinCAT Analytics Logger	MA Laser	3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True	Laserstr. 13, 40597 Düsseldorf		MP4 Steel Laser Data		ystemID
TwinCAT Analytics Logger	MA Laser	3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True					öystem Alias Broker
TwinCAT Analytics Logger	Fertig Motors	8d1ba1d7-d295-fc94-d182-09bdae66c062		False				V (Online
TwinCAT Analytics Logger	Fertig Motors	8d1ba1d7-d295-fc94-d182-09bdae66c062		False					Position
TwinCAT Analytics PLC DataLogger		7acc072f-428f-8745-c7d4-a24eb4f33d9c		False					Description Topic
TwinCAT Analytics TEST Logger	Beckhoff	91c6eab3-1abb-5593-3651-1426874cf91f		True	Hülshorstweg 20, 33415 Verl				opic Alias
TwinCAT Analytics Storage Provider		c9682ee6-b654-0881-2375-de8123db1beb		True		RetroFit			
TwinCAT Analytics Storage Provider		7acc072f-428f-8745-c7d4-a24eb4f33d9c		True		AnalyticsSolution Results 1			iping Source
TwinCAT Analytics Storage Provider		7fb4f250-c130-7d7e-0a26-71ed8cee9340		True		CloudControl			Customer
TwinCAT Analytics Storage Provider		3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True					SystemID
TwinCAT Analytics Storage Provider		3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True		TestSignals whole Image			System Alias Broker
TwinCAT Analytics Storage Provider		c5ee6cfd-4f14-5f45-dce4-7524715a9ae3		True		DataAgent Test			Online
TwinCAT Analytics Storage Provider		3f8a342a-6fac-3e76-6172-e7b5f62c0eb0		True		Bigl40 FavValues			osition
TwinCAT Analytics Storage Provider		a313c550-7537-0617-827d-c6930e90d931		True		EK Test2			Description Topic
TwinCAT Analytics Storage Provider		d180ddde-afea-78d2-9ac1-65101d008687		True		NewMachineApp			opic Alias
TwinCAT Analytics Storage Provider		3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True		LongTerm			
TwinCAT Analytics Storage Provider		3db95703-29fb-d99e-eb13-017b54677bb0	LaserPrintZG15	True		MyFavoriteData			
TwinCAT Analytics Storage Provider		56cfbec6-3ab5-c1cc-1a1d-e6f4da86adf0		True		EdgeComputingTc2			
TwinCAT Analytics Storage Provider		56cfbec6-3ab5-c1cc-1a1d-e6f4da86adf0		True		EdgeComputingTc3		~	

In the next step you can choose between Live Data and Historical Data for each MQTT Analytics client. Historical Data are only provided by the TwinCAT Analytics Storage Provider.

TwinCAT Measurement Project10 - TcXaeShell										7 5	Quick Launch (Ctrl+Q)	. • ×
File Edit View Project Build Debug TwinCAT T	TwinSAFE	PLC Team Score	Tools Window	Help								
0 • 0 13 • 11 • 11 H H K 0 10 1 7 • C ·					- 🎜			6 T - 3 0	🖂 - 🚬 🔍 🖂 🖂			
										Ŧ		
📲 Build 4024.0 (Loaded) 🔹 🛫 🗄 🔛 🔝 🕅 😂 🌂 🚳 🔍			*	* 		· 2 /	비주석	140188	EIOO [‡]			
Solution Explorer 🔹 म 🗙	Network	1* 🕫 🗙 Analytics Proj	ect*							-	Toolbox	
0 0 🕼 🗄 - To - 🗗 🏓 💻						Networks					Search Toolbox	p.
Search Solution Explorer (Ctrl+0)	<u> </u>									V	▲ Analytics - Base	^
Solution 'TwinCAT Measurement Project10' (1 project)	\square	1				lge Counter 1Ch1				67 G 🗸	N: Pointer	
Solution TwinCAT Measurement Project10 (1 project) TwinCAT Measurement Project10	l r	Input	Variables.fPulse @ tcan	alyticstest: TestSi v EN	1PTY T	hreshold Edge	률 1	Edge	FALSE			
A Malytics Project	I			A				Count	0		Edge Counter OnOff 1Ch	
 Network 1 				r				Last Event	01/01/2000 01:00:00.0	20	Edge Counter OnOff 2Ch	
Edge Counter 1Ch_1				l				Last Event	01/01/2000 01:00:00.0	×	Event Timing Analysis 1Ch	
Threshold Classificator 1Ch_1		-			Thresh	old Classificator 1Ch1		-		a/ G , 🟹	② Event Timing Analysis 2Ch	
 Inputs tcanalyticstest: TestSignals/StreamFast [1.00ms 		Input		~ O	L	evel OK / Warning:	2350	Class	NotInitialized		Timing Analysis 1Ch	
TimeLine @ tcanalyticstest: TestSignals/StreamFast [1.00ms			/			evel Warning / Alarm:	2500	Last Event Warni	01/01/2000 01:00:00.0	20	♀ Lifecycle Analysis 1Ch	
Variables.fPulse @ tcanalyticstest: TestSigna	00		1		-			·			Section 2 Contract Co	
		-						Last Event Alarm	01/01/2000 01:00:00.0		Min Max Avg 1Ch	
			- 1								Min Max Avg Interval 1Ch	
			1								Moving Average 1Ch	
			1								Moving Interval Counter 1Ch	
			1									
											Timer 1Ch	
			1								Time Clock 1Ch	
			1								F Continuous Piece Counter 1Ch	
			1								Productivity Diagnosis 3Ch	
			1								Analytics - Classification	
			1								Pointer	
			1								Threshold Classificator 1Ch	
											Threshold String Classificator 1Ch	
()	100	:0bd6e77-e2b6-4e67-a2ac									State Histogram 1Ch	
Solution Explorer Team Explorer	WB-ID: 0	cubdoe//-e2b0-4e0/-a2ac	-b927ab23d997									~
Target Browser												тģХ
ADS TcDBSrv TcAnalytics TcAnalytics File OpcUa		Enter Filter	1									
17 Y Q 2 Q		/ariables > fPulse >	1.									
🖌 🌰 tcanalyticstest	_	Name	Type ARRAY [110]	Size Category 80 Array	Full-Name Variables		ubitems Unit 0	Bit-Offse 4896	t Attributes (Instance) none	Attributes (Type)		^
🖌 🚽 LaserPrint-HTZ3			ARRAY [110]	80 Array 80 Array	Variables		0	2976	none	none		
∡ → Live Data		I A aBufferTriang		80 Array	Variables		0	5536	none	none		
TestSignals/StreamFastCompressed_Wdth8		R bEdge	BOOL	1 Primitive				344	none	none		
TestSignals/StreamFastCompressed_Wdth32		bMqttEvent	BOOL	1 Primitive				336	none	none		
TestSignals/StreamFast		(A) FAM	LREAL	8 Primitive				544	none	none		
Historical Data		64 fGrowSlov	LREAL	8 Primitive				416	none	none		
8d1ba1d7-d295-fc94-d182-09bdae66c062		🐼 fPeak	LREAL	8 Primitive	Variables.f			608	none	none		
⊳ 🚽 c9682ee6-b654-0881-2375-de8123db1beb		🚳 fPulse	LREAL	8 Primitive	Variables.f	(672	none	none		
7acc072f-428f-8745-c7d4-a24eb4f33d9c	-	IRampOnEven	LREAL	8 Primitive	e Variables.f	(352	none	none		-
Target Browser Cross Reference List Error List Output												
											Add to Source C	


You can take the variables by drag and drop into the inputs of the specific algorithm. For the most algorithm it is possible to set conditions like thresholds, time intervals, logic operators and so on. You can do these settings in the middle of each module.

Solution Explorer 👻 👎 🗙	Network 1*	🗢 🗙 Analytics Pro	ject*						-
○ ○ ☆ # - [™] > [™] > -					Networks				
Search Solution Explorer (Ctrl+ü)	_								
Solution 'TwinCAT Measurement Project10' (1 project)	-	1	V	1	Edge Counter 1Ch1	= (a]			%∕ ⊊
TwinCAT Measurement Project10		Input	Variables.fPulse @ tcanalyticstest: TestSi	EMPTY	Threshold Edge	률 1	Edge	FALSE	
 Analytics Project 							Count	0	
Network 1							Last Event	01/01/2000 01:00:00.000	
								01/01/2000 01100.00.000	
Threshold Classificator 1Ch_1 * Min Max Avg Interval 1Ch_1	-	1			eshold Classificator 1				%~ G ∑
✓ Win Wax Avg interval ICh_I ▲		Input	Count @ Edge Counter 1Ch_1	0	Level OK / Warning:	2350	Class	NotInitialized	
tcanalyticstest: TestSignals/StreamFast [1.00ms]					Level Warning / Ala	rm: 2500	Last Event Warni	01/01/2000 01:00:00.000	
🕋 TimeLine @ tcanalyticstest: TestSignals/Stre 🔐 Variables.fGrowSlow @ tcanalyticstest: TestS							Last Event Alarm	01/01/2000 01:00:00.000	
👔 Variables.fPulse @ tcanalyticstest: TestSigna		•		м	n Max Avg Interval 10	°61			~ G 🗸
		Input	Variables.fGrowSlow @ tcanalyticstest: T		Interval	Minutes v 1	Min	0	
							14-		
							Max	0	
	レス						Avg	0	
	\leq						Time Min	01/01/2000 01:00:00.000	
							Time Max	01/01/2000 01:00:00.000	
							Current Interval	00:00:00:000	
									1
Solution Explorer Team Explorer	WB-ID: c0b	d6e77-e2b6-4e67-a2a	c-b927a523d997						

Finally, your first Analytics Project is finished. To start the analysis, click on "Start Analytics". To stop the analysis, click on "Stop Analytics".

WinCAT Measurement Project10 - TcXaeShell									7 8
File Edit View Project Build Debug TwinCAT Tw		LC Team Scope Tools TwinCAT CE7 (ARMV7)	Window Help Attach	- 1		- 10 /	۵ 🕰 📾 🖓	⊡ • ₌	
🔋 Build 4024.0 (Loaded) 🔹 🖕 🔛 🧾 🖾 🧭 🖄	8 ga ga				· · · · · · · · · · · · · · · · · · ·)目 〇 🍈 🖄	Stop Analytics	
Solution Explorer 👻 🕂 🗙	Network 1*	🕫 🗙 Analytics Project*							-
○ ○ ☆ 🗂 - To - @ 🔎 🗕				'25.2	7 MB' received (1.58 N Networks	//B/s)			
Search Solution Explorer (Ctrl+ü)	_				Edge Counter 1Ch1				<i>@</i> ∕⊊ ♥
Solution 'TwinCAT Measurement Project10' (1 project) Image: TwinCAT Measurement Project10	_	Input Variables.ff	Pulse @ tcanalyticstest: TestSi 🗸	1	Threshold Edge	_ 1	Edge	False	
 Analytics Project 							Count	16	
Metwork 1 Edge Counter 1Ch_1							Last Event	18/11/2019 15:41:59.635	
Threshold Classificator 1Ch_1	-			- Thr	eshold Classificator 10	Ch1			≪ G ⊽1
Min Max Avg Interval 1Ch_1	_	Input Count @ E	dge Counter 1Ch_1 v	16	Level OK / Warning:		Class	1	
 Inputs tcanalyticstest: TestSignals/StreamFast [1.00ms] 	00				Level Warning / Alar	rm: 2500	Last Event Warni	01/01/2000 01:00:00.000	
TimeLine @ tcanalyticstest: TestSignals/Stre	0						Last Event Alarm	01/01/2000 01:00:00.000	
Variables.fGrowSlow @ tcanalyticstest: TestS Xariables.fPulse @ tcanalyticstest: TestSigna	_	1			n Max Avg Interval 1C	1.1			<i>₽</i> /G \
	-	Input Variables.f0	GrowSlow @ tcanalyticstest: T	56274	Interval	Minutes v 1	Min	0	
							Max	0	
	~						Avg	0	
	\checkmark						Time Min	01/01/2000 01:00:00.000	
	_						Time Max	01/01/2000 01:00:00.000	
							Current Interval	00:00:00:000	

Before starting Analytics or also during the runtime you can click on the button "Add Reference Scope". A Scope configuration is automatically built to fit your Analytics project.




Results of the analysis can be show in the Scope View charts by drag and drop. For example, an average value can be shown as new channel in the view. Timestamps as Marker at the x-axes to show significant values.

4.5 24h Analytics application

The last big step in the TwinCAT Analytics workflow is the continuous 24h machine analysis. It runs parallel to the machine applications in the field. To do this in a very easy way the TwinCAT Analytics Workbench is able to generate automatically a PLC code and a HTML5-based Dashboard of your Analytics configuration. Both can be downloaded to a TwinCAT Analytics Runtime (TC3 PLC and HMI Server) and provide the same analysis results as the configurator tool in engineering environment.

At first save your configuration and open the Analytics Deploy Runtime wizard. You can do this via the context menu at the Analytics Project tree item or by the Start Page.



When the wizard is open, there are some tabs available for you to click through. First one is called Solution. Here it is possible to decide how you like to use your Analytics project in PLC code: As...

- completely new solution
- part of an existing solution
- update of an existing Analytics solution

Deploy Analytics Runtin	me	×
Codegeneration: Lat	test Version ("Version 2.1")	
Solution TwinCAT F	PLC Target Results HMI Dashboard Visual Studio Summary	
 Create new Solu 	ition	
Solution Path:	C:\temp\Analytics\Test	
Solution Name:	Production	
Project Name:	MachineAnalysis	
Add to existing S	olution	
Solution Path:		
Project Name:	AnalyticsProject	
	g Project (TwinCAT Project Compare)	
Solution Path:		
Project Name:		
	Cancel Back Next	

In the TwinCAT PLC Target tab you can choose the ADS target system which runs the TwinCAT Analytics Runtime (TF3550). The generated project is immediately executable. Therefore, you can set the option Activate PLC Runtime. Also, that directly a boot project is created.

De	ploy Analytics Runtime	×
	Codegeneration: Latest Version ("Version 2.1")	
	Solution TwinCAT PLC Target Results HMI Dashboard Visual Studio Summary	_
	Target	
	Target System: <local> (172.17.251.113.1.1)</local>	
	ADS Port: 851 I Activate PLC Runtime	
	Tasks	
	"AnalyticsTask": 10 ms	
	"AnalyticsHistoricalTask": 10 ms (Generate if historical data sources are available)	
	Real-Time	
	Available CPU cores (Shared/Isolated) 4 🚖 2 🐳	
	AnalyticsTask: Core0 (Shared)	
	AnalyticsHistoricalTask: Core5 (Isolated) (If generated)	
	Cancel Back Next	

Specially for Virtual Machines it is important to run the project on isolated cores. Also, an option in this tab. The next tab Results is only necessary if you have chosen the Stream Results option in the algorithm properties. If you like to send results you can decide here in which way (local in a file/ by MQTT) and format (binary/JSON). Also, this is generated automatically and starts running after activation.

Deploy Analytics Runtime	×
Codegeneration: Latest Version ("Version 2.1")	•
Solution TwinCAT PLC Target Results HMI Dashboard	Visual Studio Summary
Create no Results	
Stream Results to MQTT Broker	
Topic: Analytics/Analysis/ResultStream	
MQTT Connection Settings 🔯 Json Form	nat 🔻
Write Results to Analytics File	
File Path:	
Max File Size: 256 😴 Sample buffer count	
Select Result Items Cyc	sleTime: User specified cycle time 🔻 5000 🚔 ms
	Cancel Back Next

A down sampling of the results is possible by setting a cycle time. The next tab is reserved for the HMI Dashboard. The prerequisite for the automatic Dashboard generation is the selection of HMI controls for the corresponding algorithms whose results are to be displayed in the dashboard.

Deploy Analytics Runtime		X
Codegeneration: Latest V	/ersion ("Version 2.1")	
Solution TwinCAT PLC T	Target Results HMI Dashboard Visual Studio Summary	
HMI generation Settin	ngs	^
🔽 Generate HMI Da	ashboard 📃 Create only HMI Project (no PLC)	
HMI Project Name:	MachineDiag	
Dashboard Options		
Dashboard Title:	Machine Diagnosis	=
Desktop Height:	864 Desktop Width: 1920	
👿 Generate Reset B	Buttons on Dashboard	
🔽 Create Startpage	3	
Dashboard Styles		
Dashboard Layout:	Dashboard Sorting:	
Witho	out Dock Control Type	
	📝 Use custom Background Image	-
	Cancel Back Next	t

You can choose for your Analytics Dashboard different options like start page with a map, layouts, sorting algorithm, own colors and logos. If you choose more languages for the Analytics controls a language switch menu will be generated as well.

Deploy Analytics Runtime		X
Codegeneration: Latest Version ("Version 2.1")	•	
Solution TwinCAT PLC Target Results HMI Dashbo	Visual Studio Summary	_
Dashboard Styles		*
Dashboard Layout:	Dashboard Sorting:	
Without Dock	Control Type	
	🔽 Use custom Background Image	
Dashboard Theme: Shiny 🔻	C:\TwinCAT\Functions\TE3500-Anal	
Select Color: Header Color	Use custom Logo No valid file	
Control Style: Flat	Use custom Map Icon No valid file	E
Languages		
	vedish azilian	•
	Cancel Back Next	


Choose one of the installed Visual Studio versions. And whether the generation should start the instance visibly or whether it should only be set up and activated in the background.

Codegeneration: Latest Version ("Version 2.1") Solution TwinCAT PLC Target Results HMI Dashboard Visual Studio Summary TwinCAT XAE Shell Visual Studio 2017 Visual Studio 2017
TwinCAT XAE Shell
TwinCAT XAE Shell
Visual Studio 2017
Cancel Back Next

Finally you find a summery.


Deploy Analytics Runtime	X
Codegeneration: Latest Version ("Version 2.1")	
Colution TwinCAT DLC Toront Double UND orthogonal Minute Summary	
Solution TwinCAT PLC Target Results HMI Dashboard Visual Studio Summary	-
Solution	
Mode: "NewSolution"	
ProjectName: "MachineAnalysis"	
Path: "C:\temp\Analytics\Test"	
WinCAT PLC Target	
AnalyticsTask => CPU Core: "4"	
Target: " <local> (172.17.251.113.1.1)"</local>	
Runtime: "851"	
AnalyticsTask: "10"	
Activate Runtime: "True"	
Create Bootproject: "True"	
AnalyticsHistoricalTask: "10"	
AnalyticsHistoricalTask => CPU Core: "5"	
Isolated CPU Cores: "2"	
Results	
Result cycle time: "10000000"	
ResultTopic: "Analytics/Analysis/ResultStream"	
BrokerSettings: " <unconfigured connectionsettings="">"</unconfigured>	
Cancel Back Deploy	

Now you can click the Deploy button to start the generation process. The PLC project and the HMI Dashboard will be generated now.



After the message Deploy Runtime succeeded you can find a new Visual Studio®/XAE Shell instance on your desktop. The new Solution and both Projects are generated.

32



5 Technical introduction

5.1 Basic Concepts

Variables and Datatypes

There are several types of variables that can be logged. Variables that are part of:

- PLC or NC process images
- PLC programs
- process images of devices e.g. an EtherCAT master and
- data areas of generic TcCom objects.

Moreover, they may be of any datatype defined in IEC 61131 or the C++ standard in case of generic TcComobjects.

Structured datatypes may recursively contain other structured datatypes and may be logged as a whole or partially. For more information on this topic, refer to the Configuration section.

Modes of Operation

This documentation makes use of the terminology and concepts described in the MQTT-section. Please refer to that section for general information about the protocol.

A key concept of TwinCAT Analytics are streams, which form the basic unit of transaction between a data source and destination. One data logger can control several streams.

A stream may comprise four components:

- · stream description
- stream Tx-description
- symbol info
- and stream data.

In **MQTT-mode**, Analytics participants coordinate by means of the first three components using an MQTT broker and a specific MQTT topic for each component. The **topics** are generally structured as illustrated in the following table, whereat <>-brackets indicate variables as opposed to the other parts that are fixed.

Component	Topic Structure	Format	Purpose
Description	<maintopic>/<streamtopic>/Desc</streamtopic></maintopic>	JSON	Informs if there is a stream source online or offline. Includes timestamp of info.
Tx- Description	<maintopic>/<streamtopic>/Bin/Tx/ Desc</streamtopic></maintopic>	JSON	Informs about the transmission parameters when a stream source is active transmitting data.
Symbol Info	<maintopic>/<streamtopic>/Bin/Tx/ Symbols</streamtopic></maintopic>	Binary	Contains meta information about the variables i.e. excluding the actual value.
Data	<maintopic>/<streamtopic>/Bin/Tx/Data</streamtopic></maintopic>	Binary	Contains the plain variable values.

The main topic is the only subtopic that can freely be set by the user.

A stream can be **started** and **stopped**. The system manager configuration allows a stream to be started by default as soon as TwinCAT starts in run-mode. Additionally, streams can be started and stopped from PLC code.

When connected to a broker, the logger first sends the stream description followed by the Tx-description and symbol info as soon as the stream starts. This enables recipients to take all measures that are needed before data arrives. Finally, data is sent cyclically.

For the **file-mode**, the TwinCAT Boot directory on the target device is used as a base for a dedicated Analytics directory, which in turn contains one subdirectory per stream as soon as the respective TwinCAT project has been activated. Inside the stream's directory, a dedicated .tas-file holds the symbol info whereas .tay-files, which are created cyclically, contain the stream data.

Relation of Logger and Streams

One data logger can control several streams. As will be described more detailed in the Configuration section a user can add one or more data loggers to the Analytics configuration. Streams then are added automatically, depending on what variables are available to be logged. To understand how streams are assigned to a logger it is useful to understand that every stream has specific characteristics. One characteristic, the **cycle time**, comes from the fact that every variable that is acted upon cyclically is subject to a cyclic task; therefore, cycle times that underlie different variables can vary. Since a stream has a fixed cycle time by definition and to decouple tasks with the same cycle time, one stream is created for every task that drives relevant variables. Additionally, it is purposeful to further divide streams depending on the **stream source**, meaning the origin PLC instance or TcCom object. This enables users to send variables of different sources to different MQTT topics and start/stop the transmission independently. Eventually it all comes down to the following scheme:


For every stream source and every task that drives variables of that source, a stream is created.

When configuring the data logger, there are configuration parameters that all streams have in common and those that are stream specific. The logger specifies the destination, the compression method, MQTT credentials etc. whereas e.g. the data size and start/stop-functionality are stream specific.

In most cases it might not be necessary to send or write data every task cycle, so the data of a stream recorded in a cycle, a so-called **sample**, can be buffered before sending it to the broker or writing it to file. The number of samples in a buffer and thus the cycle time of a **buffer** being sent/written can be configured. Moreover, the number of buffers in a file and thus the **file size** can be configured.

5.2 MQTT

MQTT(Message Queueing Telemetry Transport) is a publisher/subscriber-based communication protocol, which enables message-based transfer between applications. A central component of this transfer type is the so-called message broker, which distributes messages between the individual applications or the sender and receiver of a message. The message broker decouples the sender and receiver, so that it is not necessary for the sender and receiver to know their respective address information. During sending and receiving all communication devices contact the message broker, which handles the distribution of the messages.



Payload

The content of an MQTT message is referred to as payload. Data of any type can be transferred, e.g. text, individual numerical values or a whole information structure.

Message payload formatting


Note that the data type and the formatting of the content must be known to the sender and receiver side, particularly when binary information (alignment) or strings (with or without zero termination) are sent.

Topics

If a message broker is used that is based on the MQTT protocol, sending (publish mode) and subscribing (subscribe mode) of messages is organized with the aid of so-called topics. The message broker filters incoming messages based on these topics for each connected client. A topic may consist of several levels; the individual levels are separated by "/".

Example: Campus / Building1 / Floor2 / Room3 / Temperature

When a publisher sends a message, it always specifies for which topic it is intended. A subscriber indicates which topic it is interested in. The message broker forwards the message accordingly.



Communication example 1 from the diagram above:

- An application subscribes to "topic1".
- A controller publishes a message to "topic1".
- The message broker forwards the message to the application accordingly.

Communication example 2 from the diagram above:

- A controller subscribes to "topic2".
- An application publishes a message to "topic2".
- The message broker forwards the message to the controller accordingly.

Wildcards

It is possible to use wildcards in conjunction with topics. A wildcard is used to represent part of the topic. In this case a subscriber may receive messages from several topics. A distinction is made between two types of wildcards:

- Single-level wildcards
- Multi-level wildcards

Example for single-level wildcard:

The + symbol describes a single-level wildcard. If it is used by the subscriber as described below, for example, corresponding messages to the topics are either received by the subscriber or not.

- The receiver subscribes to Campus/Building1/Floor2/+/Temperature
- The publisher sends to Campus/Building1/Floor2/Room1/Temperature OK
- The publisher sends to Campus/Building1/Floor2/Room2/Temperature OK
- The publisher sends to Campus/Building42/Floor1/Room1/Temperature NOK
- The publisher sends to Campus/Building1/Floor2/Room1/Fridge/Temperature NOK

Example for multi-level wildcard:

The # symbol describes a multi-level wildcard. If it is used by the subscriber as described below, for example, corresponding messages to the topics are either received by the subscriber or not. The # symbol must always be the last symbol in a topic string.

- The receiver subscribes to Campus/Building1/Floor2/#
- The publisher sends to Campus/Building1/Floor2/Room1/Temperature OK
- The publisher sends to Campus/Building1/Floor2/Room2/Temperature OK
- The publisher sends to Campus/Building42/Floor1/Room1/Temperature NOK
- The publisher sends to Campus/Building1/Floor2/Room1/Fridge/Temperature OK
- The publisher sends to Campus/Building1/Floor2/Room1/Humidity OK

QoS (Quality of Service)


QoS is an arrangement between the sender and receiver of a message with regard to guaranteeing of the message transfer. MQTT features three different levels:

- 0 not more than once
- 1 at least once
- · 2 exactly once

Both types of communication (publish/subscribe) with the message broker must be taken into account and considered separately. The QoS level that a client uses for publishing a message is set by the respective client. When the broker forwards the message to client that has subscribed to the topic, the subscriber uses the QoS level that was specified when the subscription was established. This means that a QoS level that may have been specified as 2 by the publisher can be "overwritten" with 0 by the subscriber.


QoS-Level 0

At this QoS level the receiver does not acknowledge receipt. The message is not sent a second time.




QoS-Level 1

At this QoS level the system guarantees that the message arrives at the receiver at least once, although the message may arrive more than once. The sender stores the message internally until it has received an acknowledgement from the receiver in the form of a PUBACK message. If the PUBACK message fails to arrive within a certain time, the message is resent.



QoS-Level 2

At this QoS level the system guarantees that the message arrives at the receiver no more than once. On the MQTT side this is realized through a handshake mechanism. QoS level 2 is the safest level (from a message transfer perspective), but also the slowest. When a receiver receives a message with QoS level 2, it acknowledges the message with a PUBREC. The sender of the message remembers it internally until it has received a PUBCOMP. This additional handshake (compared with QoS 1) is important for avoiding duplicate transfer of the message. Once the sender of the message receives a PUBREC, it can discard the initial publish information, since it knows that the message was received once by the receiver. In other words, it remembers the PUBREC internally and sends a PUBREL. Once the receiver has received a PUBREL, it can discard the previously remembered states and respond with a PUBCOMP, and vice versa. Whenever a package is lost, the respective communication device is responsible for resending the last message after a certain time.



Security

When a connection to the message broker is established, it is possible to use security mechanisms such as TLS, in order to encrypt the communication link or to realize authentication between client and message broker.

Sources

For further and more detailed information about MQTT we recommend the following blog series:

HiveMq blog: http://www.hivemq.com/blog/mqtt-essentials/ (the main basis for this article)

5.3 Data Compression

In order to reduce the amount of data to be sent without reducing the amount of information and thus enhance the performance, a compression method derived from the Run Length Encoding method can be used. It utilizes the fact, that data of two consecutive samples in a buffer may not vary in parts. Thus knowing what parts of a previously sent buffer are equal in conjunction with the varying data, a recipient can reconstruct the next buffer without the need to receive the whole buffer. After sending the first buffer uncompressed, the logger constructs the compressed buffer by comparing user-specified units of data (e.g.

every byte, every 8 byte etc.) one after another. The logger counts the amount of data units (called Compression Compare Width) that are equal and places this information in the buffer instead of the data. Dependent on the kind of data this can lead to a data saving or overhead. To decide whether a compression is purposeful or not the user is provided with a data compression saving value, which can be found on the Online-tab of every stream dialog window. A positive value indicates saving and a negative value indicates overhead.


6 Configuration

6.1 Basic settings


To configure the TwinCAT Analytics Logger the user is provided with a dedicated Analytics configuration inside of a XAE project.

Solution Explorer	▼ □ ×
○ ○ ☆ '⊙ - ♂ <i>▶</i> -	
Search Solution Explorer (Ctrl+ü)	، م
 Solution 'MeasurementSamplePLC' (1 project) MeasurementSamplePLC SYSTEM MOTION PLC SAFETY C++ 	
ANALYTICS	
Þ <mark>⊠</mark> 1/O	
Solution Explorer Team Explorer	

To add a data logger choose the respective item in the context menu of this configuration node.



This may either result in the additional Data Logger node alone or subordinate stream nodes in case there already are variables that can be logged.



By double clicking the new Data Logger node the editor window will be open. In the Parameter tab you can make your specific Analytics Logger settings.

lution Explorer 🔹 म 🗙	MeasurementSamplePLC 👳 🗙				
o 🕼 🐻 - 🗗 🗲 🗕	Parameter (Init) TIs				
arch Solution Explorer (Ctrl+ ü) 🖉 🗸	Name	Value	CS	Туре	PTCID
Solution 'MeasurementSamplePLC' (1 project) MeasurementSamplePLC	MQTT Host Name	127.0.0.1		STRING(80)	0x02020113
SYSTEM	MQTT Tcp Port	1883		UINT	0x02020103
MOTION	MQTT Main Topic			STRING(255)	0x02030008
PLC	MQTT Client ID			STRING(80)	0x02020101
SAFETY	MQTT User Name			STRING(255)	0x02020106
A ANALYTICS	MQTT Password			STRING(80)	0x02020107
😹 Data Logger 1	MQTT Data Format	IOT FORMAT FILE	_	IOT_FORMAT	0x02020114

- MQTT Host Name: Provide here the host name or IP address of your native MQTT Message Broker
- MQTT Tcp Port: Here set the Tcp port for the communication. Default MQTT port: 1883
- **MQTT Main Topic:** It is possible to provide an own and individual main topic. Sample: Beckhoff/Verl/ Production/Drives/Machine5 – the Analytics Logger will add automatically his own specific subtopics: Beckhoff/Verl/Production/Drives/Machine5/**Bin/Tx/Data**
- **MQTT Client ID:** The client identifier is an identifier of each MQTT client connecting to a native MQTT Message Broker. It should be unique per Broker.
- MQTT User Name: MQTT allows to send a username for authenticating the client.
- **MQTT Password:** MQTT also allows to send a password for authenticating the client and authorization.
- Data Format: Here the user can choose between *IOT_FORMAT_FILE* and *IOT_FORMAT_BINARY*. By using the *FILE* format the Analytics Logger store the data in local binary files and all settings above are not necessary anymore. The files will be stored in C:\TwinCAT\3.1\Boot\Analytics. By using *BINARY* the data will send to the configured MQTT Message Broker.

It is possible to have multiple Logger in one TwinCAT project to communicate data to different MQTT Message Broker or to have partly a storage in a local binary file.

6.1.1 TLS

TLS (Transport Layer Security) provide a secure communication channel between a client and a server. At its core, TLS is cryptographic protocols which use a handshake mechanism to negotiate various parameters to create a secure connection between the client and the server. The TwinCAT Analytics Logger is supporting TLS version 1.2.



MQTT communication with TLS

By the usage of certificates the TCP port 8883 is exclusively reserved for MQTT over TLS!

On the TLS tab of the Data Logger your first choice is the TLS Mode in a drop down box. Depending on the Message Broker it is possible to use different TLS mechanism/modes. The Analytics Logger is supporting the modes CA Certificates, CA Certificates & Client Certificate and the Preshared Key (PSK) mode.

MeasurementSamplePLC - Microsoft Visual S	Studio (Administrator)
File Edit View Project Build Debug	TwinCAT TwinSAFE PLC Team Tools Test Scope Analyze Window
🛛 🗢 - 😂 🖏 - 🔁 - 🖆 🔛 🖉 👗 🗗 🤅	🗊 🤊 - 🖓 - 🕅 Release - TwinCAT RT (x64) - 🕨 Attach
🗄 🔛 🧧 🖉 🔨 🌀 🚺 🐾 🛛 <local></local>	🗸 🚽 ScopeSample 🔹 1 🔹 🔁 🗼 🕿 🚭 👘 😤 🏌
Solution Explorer 🛛 👻 🕂 🗙	MeasurementSamplePLC + X Variables
○ ○ 🏠 [™] 0 → 🗗 🖋 🗕	Context Parameter (Init) Data Area TIs
Search Solution Explorer (Ctrl+ü)	
 Solution 'MeasurementSamplePLC' (1 project MeasurementSamplePLC SYSTEM MOTION PLC ScopeSample ScopeSample Project ScopeSample Instance SAFETY C++ ANALYTICS Data Logger 1 Stream (ScopeSample Instance Stream (ScopeSample Instance Mappings 	Tis Mode: No Security No Security CA Certificate CA Certificate & Client Certificate Preshared Key(PSK)


CA Certificate

Encryption and authentication via TLS can also be accomplished through a certificate authority (CA). The CA provides a signature via the public key for all communication clients. In this case an MQTT client connect to a Message Broker without a dedicated client certificate.

MeasurementSamplePLC - Microsoft Visual	Studio (Administrator)
File Edit View Project Build Debug	TwinCAT TwinSAFE PLC Team Tools Test Scope Analyze Window
🖉 - 🗢 🏗 - 🖆 - 🍟 🗳 🕹 🗗	🗈 🤊 - 🖓 - 🕅 Release - TwinCAT RT (x64) - 🕨 Attach
🖗 🔛 🔤 🖉 🖄 🌀 🚺 🗞 🛛 	🗸 🚽 ScopeSample 🔹 1 🔹 🔁 🕨 🖘 🖘 🖿
Solution Explorer 🛛 🔻 🕂 🗙	MeasurementSamplePLC + X Variables
© ⊃ 🏠 ™ - 🗗 / 🖊 🗕	Context Parameter (Init) Data Area TIs
Search Solution Explorer (Ctrl+ü)	
Solution 'MeasurementSamplePLC' (1 projec	TIs Mode: CA Certificate
MeasurementSamplePLC	CA Certificate: C:\Beckhoff\Project Test and Attachments\Internal\PD\2018_01_09\ca.
SYSTEM MOTION	Don't check identity of broker (insecure)
ScopeSample	
ScopeSample Project	
ScopeSample Instance	
SAFETY	
C++	
 ANALYTICS Analytics Data Logger 1 	
Stream (ScopeSample Instance	
⊿ 🔽 I/O	
The Devices	
Mappings	

CA Certificate & Client Certificate

Encryption and authentication via TLS can also be accomplished through a certificate authority (CA). The CA provides a signature via the public key for the message broker (the so-called server key) and usually also for all connecting clients. All communication devices can then trust each other, because the issuing certificate authority is trusted.




Preshared Key (PSK)

The TLS PreSharedKey (PSK) method offers a simple option for realizing encryption between client and message broker. Client and broker recognize a common password, which is used to encrypt and decrypt the packages.

MeasurementSamplePLC - Microsoft Visual S File Edit View Project Build Debug ○ • ○ 12 • 12 • 12 • 12 • 12 • 12 • 12 • 12 •	TwinCAT TwinSAFE PLC Team Tools Test Scope Analyze Window
Solution Explorer Image: A marked bit is a marke	MeasurementSamplePLC ⇒ Variables Context Parameter (Init) Data Area TIs TIs Mode: Preshared Key(PSK) • Identity: myldentity • • @ Password: • • @ Hex Binary Key: A2FF7AC •

6.2 Data Streams

If variables are available for recording they will be shown automatically as a so called Stream. At the moment it is possible to record data directly from the EtherCAT process image or from the PLC application.



BECKHOFF


PLC Application:

If variables from PLC should recorded by the Analytics Logger, the user must set an attribute in front of each variable in the variable declaration.

The attribute syntax is: {attribute 'TcAnalytics'}


🖗 🔛 🔤 🖉 🔨 🌀 🚺 🏪 🛛 <local></local>		▼	- -] ▶ ■ € ‡ ? ‡ %
Solution Explorer 🔹 👎 🗙	Variables	→ × MeasurementSamplePLC	-
C O 🟠 🐻 - 🗗 🛐 🖌 🗕	■ 1	VAR_GLOBAL	
Search Solution Explorer (Ctrl+ü)	2	{attribute 'TcAnalytics'] fAM	LREAL:
Solution 'MeasurementSamplePLC' (1 project)	4	{attribute 'TcAnalytics'	
MeasurementSamplePLC	5	fPeak	LREAL;
Weastrementsampler LC SYSTEM	6	{attribute 'TcAnalytics']	
MOTION	7	fPulse	: LREAL;
	8	{attribute 'TcAnalytics']	}
CopeSample	9	fSawtooth	: LREAL;
ScopeSample ScopeSample	10	{attribute 'TcAnalytics']	
External Types	11		: LREAL;
References	12	{attribute 'TcAnalytics']	
DUTs	13		: LREAL;
V GVLs	14 15	{attribute 'TcAnalytics']	
GVLS GVL_Constants	15	fStairs {attribute 'TcAnalytics'	: LREAL;
Variables	17		: LREAL;
POUs	18	IIIIangulai	. LKEAL,
B_ FB_ArrayConverter (FB)	19	aBufferAM	ARRAY[1cOversamples]
► FB_FunctionGenerator (FB)			: ARRAY[1cOversamples]
MAIN (PRG)	21		ARRAY[1cOversamples]
	22		ARRAY[1cOversamples]
 VISUS PIcTask (PIcTask) 	23	aBufferSawtooth	ARRAY[1cOversamples]
ScopeSample.tmc	24	aBufferSine	ARRAY [1cOve 100 🔍 👻
ScopeSample.Inc			
Scopesample instance			

As already described a new stream is automatically add to the Analytics Logger configuration **after rebuild** of the PLC project. In the stream a *Selection* tab is available to choose finally the variables by checkboxes who should be recorded.



Process Image:

If an EtherCAT process image is available in the given configuration, an additional stream will be shown under the Data Logger tree node.



On the Selection tab the user can choose again the values who should be recorded by the Analytics Logger.

Solution Explorer - P X	▼ ↓ ScopeSample ↓
Solution Explorer	Variables MeasurementSamplePLC × Selection Analytics Image: Construction of the status of the

Start Record

With the activation of the TwinCAT configuration the Analytics Logger starts logging. Depending on the basic settings to a MQTT Message Broker or into a local binary file. By the given format there are different settings possibilities on the Data Handling tab of each Stream. See therefore the following chapter.

6.2.1 Data Handling

In the Data Handling tab you can make general settings for the package size of the recorded data. Depending on the given data format it gives additional settings.

election Analytics				
Data Size:	40	(Bytes)		
Max ADS Buffer:	32 🌲	2	(KB)	32 ms
Max File Size:	0	1	(KB)	0 s
Ring Buffer				
File Count:	0] (KB)	
Queue messag Use file queu Queue Size:	ges when disconned Je 0 <u>×</u>	cted) (KB)	

Data Size: This is a read-only value and provide the size of the given variable selection for this stream.

Max ADS Buffer: Here you can set the number of buffered cycles before write to file or send to Message Broker. By 1ms cycle time and 32 buffers the Analytics Logger buffered 32ms before operated. It is an individual setting depending on the system resources.

Max File Size: Only available by *IOT_FORMAT_FILE*. You can give the maximum file size before starting with a new file. The files will be stored under C:\TwinCAT\3.1\Boot\Analytics.

Data format: MQTT

If the data format is *IOT_FORMAT_BINARY* it is possible to activate an additional checkbox for queuing messages by disconnect.

ta Size:	40		(Bytes)		
x ADS Buffer:	32	*	2	(KB)	32 ms
ax File Size:	512	*	769	(KB)	16.384 s
√ Ring Buffer					
File Count:	5	*	3841	(KB)	1:21 m

File Store: If this option is activated the queued messages will stored in a temporary file at the hard disk. Otherwise the data will be stored in the RAM when connection to the Message Broker is disconnected.

Queue Size: Is the number of configured ADS Buffer which should be stored in the case of a lost connection.

Data format: File

If the data format is *IOT_FORMAT_FILE* it is possible to activate an additional checkbox for a ring buffer.

MeasurementSamplePLC 🗢 🗙 Variables							
Selection Analytics							
Data Size:	40	(Bytes)					
Max ADS Buffer:	32 🚖	2	(KB)	32 ms			
Max File Size:	512 🚔	769	(KB)	16.384 s			
Ring Buffer							
File Count:	5	3841	(KB)	1:21 m			
Queue messages when disconnected Use file queue Queue Size: 0 (KB)							

File Count: You can set up a ring buffer system for the binary files. With the File Count parameter you can give a number of files who should be part of the ring buffer. The ring buffer time depends on the given Max File Size.

6.3 Using the Programming Interface

As described in the Technical Introduction a stream can be started and stopped from PLC code using Structured Text. For that, the streams of a data logger, themselves being TcCom-objects provide an interface called *ITcAnalyticsStream* comprising two methods, *StartAnalyticsStream()* and *StopAnalyticsStream()*. Follow the following steps to use the interface, the code samples may be useful, too:

Declare a variable of the type *ITcAnalyticsStream* and another one of the type *OTCID* for the object ID of the correspondent stream. For diagnostic purposes, an *HRESULT* variable is advisable.

```
HR : HRESULT := S_OK;
{attribute 'tcinitsymbol'}
oidPlcStream1 : OTCID;
ipPlcStream1 : ITcAnalyticsStream;
```

Next, add the attribute 'tcinitsymbol' above the OTCID variable. This way, it doesn't need to be initialized statically in the source code, instead it be initialized at configuration time by double clicking the PLC instance node in the project tree and selecting the relevant stream in the combo box as illustrated in the following picture.

Ľ	ataLoggerStartStop 9 X MAIN		/	
I	Object Context Parameter (Init) Data Area Symbol Initialization			
L	Name	Value	Unit	Туре
L	MAIN.oidPlcStream1	02030011 'PicStream1'		OTCID
		00000000 02010030 PICTask' 0200031 1/0 Jale Task' 050000 PICAurtask'		
l		02030011 'PicStream1' 08502000 'StartStopSample Instance'	J	

Fig. 1:

After that, get an interface pointer using following the TcCom-object server method and the interface's IID.

Now you can use the interface pointer to call interface's methods. As shown in the following example:

```
IF ipPlcStream1 <> 0 THEN
    IF bStartPlcStream1 THEN
        ipPlcStream1.StartAnalyticsStream();
        bStartPlcStream1 := FALSE;
    END_IF
    IF bStopPlcStream1 THEN
        ipPlcStream1.StopAnalyticsStream();
        bStopPlcStream1 := FALSE;
    END_IF
END_IF
END_IF
```

The stream is started in the same cycle StartAnalyticsStream() is called and will include the logged variable values. The stream is stopped in the same cycle StopAnalyticsStream() is called but *will not* include the variable values of this cycle.

In the Samples section of this documentation you can find a sample program that includes the here presented code snippets.

7 Samples

Data Logger Start/Stop stream from PLC code sample:

https://infosys.beckhoff.com/content/1033/tf3500_tc3_analytics_logger/Resources/zip/6904617099.zip

8 Appendix

8.1 **FAQ - frequently asked questions and answers**

In this section frequently asked questions are answered in order to make your work with TwinCAT Analytics Logger easier. If you have further questions, please contact our support team <u>support@beckhoff.com</u>.

Should I always use TLS with MQTT? [▶ 54]

Is it possible to have multiple connections? [> 54]

Is it possible to control the Analytics Logger by a PLC function block? [> 54]

?Should I always use TLS with MQTT?

!Yes, you should if you can. If you can afford the overhead in CPU and bandwidth, then a secure communication channel is invaluable. Depending on the general CPU performance it could be possible to have a noticeable reduction of communication performance.

?ls it possible to have multiple connections?

!Yes, you can connect the Analytics Logger at the same time to different Message Broker just by adding a new instance of the Logger. Also it is possible to have one instance of the Logger for an MQTT communication to a Message Broker and at the same time one instance for writing data into Analytics File to the local system.

?Is it possible to control the Analytics Logger by a PLC function block?

!There is no special function block to control the Analytics Logger. But you can use an interface of the Analytics Logger to control him with easy commands like start and stop from the PLC. How to do see <u>this</u> [$\underbrace{b \ 51}$] cheapter.

More Information: www.beckhoff.com/tf3500/

Beckhoff Automation GmbH & Co. KG Hülshorstweg 20 33415 Verl Germany Phone: +49 5246 9630 info@beckhoff.com www.beckhoff.com

