
Class Web: WWW.MWFTR.COM/emblab.html

EECE456 Embedded Systems Design Lab Electrical and Computer Engineering Howard University Instructor: Dr. Charles Kim

Accessing Linux Console of Galileo¹

Galileo Gen 2:

Accessing Linux Console means we can run regular Linux commands directly on the Galileo board. A special serial cable is required to connect a computer to Galileo Gen 2. For Galileo Gen 1 Board, read the next page for the proper type of connector. This special serial cable is a FTDI cable with a 6-pin connector and +3.3 V serial to USB as illustrated below. Thankfully, this cable is included in the Grove Kit box. When we connect the special serial cable, we make sure the inline connector connects pin 1 (black) to pin 1 of the FTDI connector (which is indicated by a little white triangle) on Galileo Gen 2. We connect the other end of the cable to a computer.



The next step tests the cable with Galileo Gen 2 board. By the way, to run a Linux console with the cable, we need to install the software on a computer in order to pen a serial channel with Galileo Gen 2. The software we need depends on our operational system and our preference. This step explores **putty** for Windows, **minimcom** for Linux, and **screen** for Max OS. Note that **screen** is also available on Linux, and **minicom** is also available in Mac OS.

Now jump to P3.

¹ This instruction is based on "Intel Galileo Gen 1 and Gen 2 - API Features and Arduino Projects for Linux Programming" by Ramoel Ramon, Apress Open.

Galileo Gen 1:

For Galileo (Gen 1), a very special type of connector is required: 3.5mm stereo jack to USB FTDI cable converter cable as shown in the left figure below. And the 3.5 mm jack is to be inserted to the Gen 1 board as indicated in the right figure below, and the other end (USB) to a computer.



The next step tests the cable with Galileo Gen 1 board. By the way, to run a Linux console with the cable, we need to install the software on a computer in order to pen a serial channel with Galileo Gen 1. The software we need depends on our operational system and our preference. This step explores **putty** for Windows, **minimcom** for Linux, and **screen** for Max OS. Note that **screen** is also available on Linux, and **minicom** is also available in Mac OS.

Go to the next page.

Windows

The following steps explain how to set up the Linux console on Windows:

- After you insert the cable, wait for a few seconds so that the USB is enumerated. Then open the Windows Device Manager by choosing Start ➤ Control Panel ➤ Hardware and Sound ➤ Device Manager. You can also press the Windows key and "R" at same time, and then type devmgmt.msc.
- **2.** In the Device Manager, check the COM port available under the Ports section. Figure 1-20 shows an example of a COM port enumerated as COM5.




Figure 1-20. Intel Galileo COM port on Windows

- 3. Download putty and install it on your Windows machine. You can download it from http://www.chiark.greenend. org.uk/~sgtatham/putty/download.html.
- 4. Execute putty. Select the Serial protocol and enter the COM port number. Then click the Open button, as shown in Figure 1-21.

Category:	Basic options for your PuTTY session	
 Session Logging Terminal Keyboard Bell Features Window Appearance Behaviour Translation Selection Colours Connection Proxy Telnet Rlogin SSH Serial 	Basic options for your Pull I I session	
	Specify the destination you want to connect to	
	Serial line	Speed
	COM36	115200
	Connection type: Raw Telnet Rlogin SSH	Serial
	Load, save or delete a stored session Saved Sessions	
	SERIAL	
	Default Settings	Load
	SERIAL SERIAL_EDISON SSH SSH_EDISON	Save
		Delete
	Close window on exit: Always Never Only on clean exit	

Figure 1-21. Configuring putty to open the Linux console

5. Finally, to access the Linux console, you type username root and press Enter. You will then have access to the Linux console, as shown in Figure 1-22.




Figure 1-22. The Linux serial console

Ubuntu Linux

The procedure to set up Intel Galileo's Linux console on a Linux computer is easy. As mentioned, serial communication on Linux computers is based on the minicom software.

The following steps are necessary to get the Linux console working:

- 1. After you insert the cable, wait for a few seconds for the USB to be enumerated.
- 2. Open a Linux terminal. You can press Ctrl+T to do this.
- **3.** Check the port by typing the command dmesg | grep tty. For example, Figure 1-23 shows the port enumerated as ttyUSB0.



Figure 1-23. Checking the USB port enumerated on the Ubuntu terminal

4. Finally, to access the Linux console, you typing the sudo minicom --device /dev/ttyUSB0 command. The terminal will open. You need to use the username root.

Mac OSX

The following steps describe how to set up the Linux console on Mac OSX.

- 1. After you insert the cable, wait for a few seconds so that the USB is enumerated.
- 2. Open an OSX terminal. You can press **#** and the spacebar at same time to open the Spotlight text box. Then type terminal and press Enter.
- **3.** In the terminal, check what is the serial port enumerated as following command:

~\$ ls /dev/tty.usb*
/dev/tty.usbserial-A603HVUT

 Finally, you can access the Linux console by typing screen /dev/<YOUR SERIAL HERE> 115200 into the terminal. For example

~\$ screen /dev/tty.usbserial-A603HVUT 115200

5. The console will open. You need to use the username root.

Exploring the Linux Console

Try to run some Linux commands. To check which board you have, you can run the following command:

root@clanton:~# cd /sys/firmware/board_data/ root@clanton:/sys/firmware/board_data# cat flash_version 0x01000300

As you can see, when this chapter was written, my board was using firmware 1.0.3. The hexadecimal sequence is decoded as 01.00.03.00, 01.00.03, or 1.0.3, as expected.

A second interesting test is to check your platform name. Run the following commands if your board is Intel Galileo:

```
root@clanton:~# cd /sys/devices/platform/Galileo
root@clanton:/sys/devices/platform/Galileo# cat modalias
platform:Galileo
```

If your board is Intel Galileo Gen 2, the following commands work:

```
root@clanton:~# cd /sys/devices/platform/GalileoGen2/
root@clanton:/sys/devices/platform/GalileoGen2# cat modalias
platform:GalileoGen2
```

The releases provided by Intel contain the busybox software utility. It provides about 300 commands that can be executed in the Linux console. If you type busybox and press Enter, you will be able to see the supported commands.

```
root@clanton:/sys/devices/platform/GalileoGen2# busybox
BusyBox v1.20.2 (2014-08-22 10:41:19 PDT) multi-call binary.
Copyright (C) 1998-2011 Erik Andersen, Rob Landley, Denys Vlasenko
and others. Licensed under GPLv2.
See source distribution for full notice.
```

```
Usage: busybox [function] [arguments]...
or: busybox --list
or: function [arguments]...
```

BusyBox is a multi-call binary that combines many common Unix utilities into a single executable. Most people will create a link to busybox for each function they wish to use and BusyBox will act like whatever it was invoked as.

Currently defined functions:

[, [[, acpid, ar, arp, arping, ash, awk, basename, blkid, blockdev, bootchartd, brctl, bunzip2, bzcat, cat, chgrp, chmod, chown, chroot, chrt, clear, cmp, cp, cpio, cttyhack, cut, date, dc, dd, deallocvt, depmod, df, diff, dirname, dmesg, dnsdomainname, du, dumpkmap, echo, egrep, env, expr, false, fdisk, fgrep, find, findfs, flock, free, fsck, fsync, ftpd, ftpget, ftpput, fuser, getty, grep, gunzip, gzip, halt, hd, head, hexdump, hostname, hwclock, id, ifconfig, ifdown, ifup, insmod, ionice, iostat, ip, kill, killall, klogd, less, ln, loadkmap, logger, login, logname, logread, losetup, ls, lsmod, lsof, lspci, lsusb, md5sum, mdev, mkdir, mkfifo, mknod, mktemp, modprobe, more, mount, mv, nc, netstat, nice, nohup, nslookup, od, patch, pidof, ping, ping6, pivot root, pmap, poweroff, printf, ps, pwd, rdate, readlink, realpath, reboot, renice, reset, resize, rm, rmdir, rmmod, route, run-parts, sed, seq, setconsole, setserial, setsid, sh, sleep, sort, start-stop-daemon, stat, strings, stty, sulogin, switch root, sync, sysctl, syslogd, tail, tar, tcpsvd, tee, telnet, telnetd, test, tftp, time, timeout, top, touch, tr, traceroute, traceroute6, true, tty, udhcpc, umount, uname, uniq, unzip, uptime, usleep, vconfig, vi, watch, wc, wget, which, who, whoami, xargs, yes, zcat, zcip

If you need to execute one of these commands, you simply type the desired command.

Testing the Data Cables

The high-speed USB 2.0 male-to-micro USB cable, or simply the data cable, is used to transfer and debug the sketches. Testing this cable is covered in Chapter 3 because doing so requires the installation of the IDE.

